Using ADOBE COLDFUSION BUILDER



© 2010 Adobe Systems Incorporated. All rights reserved.

Using Adobe® ColdFusion® Builder™

This user guide is protected under copyright law, furnished for informational use only, is subject to change without notice, and should not be construed as a commitment by Adobe Systems Incorporated. Adobe Systems Incorporated assumes no responsibility or liability for any errors or inaccuracies that may appear in the informational content contained in this guide.

This user guide is licensed for use under the terms of the Creative Commons Attribution Non-Commercial 3.0 License. This License allows users to copy, distribute, and transmit the user guide for noncommercial purposes only so long as (1) proper attribution to Adobe is given as the owner of the user guide; and (2) any reuse or distribution of the user guide contains a notice that use of the user guide is governed by these terms. The best way to provide notice is to include the following link. To view a copy of this license, visit https://creativecommons.org/licenses/by-nc-sa/3.0/

Adobe, the Adobe logo, Adobe AIR, ColdFusion, ColdFusion Builder, and Flash Builder are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States and/or other countries.

Java is a trademark or registered trademark of Sun Microsystems, Inc. in the United States and other countries. Macintosh is a trademark of Apple Inc., registered in the United States and other countries. Windows is either a registered trademark or a trademark of Microsoft Corporation in the United States and/or other countries. All other marks are the property of their respective owners.

Updated Information/Additional Third Party Code Information available at http://www.adobe.com/go/thirdparty.

Portions include software under the following terms:

This product includes software developed by the Apache Software Foundation (http://www.apache.org/).

This product contains either BSAFE and/or TIPEM software by RSA Data Security, Inc.

Adobe Systems Incorporated, 345 Park Avenue, San Jose, California 95110, USA.

Notice to U.S. Government End Users. The Software and Documentation are "Commercial Items," as that term is defined at 48 C.F.R. §2.101, consisting of "Commercial Computer Software" and "Commercial Computer Software Documentation," as such terms are used in 48 C.F.R. §12.212 or 48 C.F.R. §227.7202, as applicable. Consistent with 48 C.F.R. §12.212 or 48 C.F.R. §\$227.7202-1 through 227.7202-4, as applicable, the Commercial Computer Software and Commercial Computer Software Documentation are being licensed to U.S. Government end users (a) only as Commercial Items and (b) with only those rights as are granted to all other end users pursuant to the terms and conditions herein. Unpublished-rights reserved under the copyright laws of the United States. Adobe Systems Incorporated, 345 Park Avenue, San Jose, CA 95110-2704, USA. For U.S. Government End Users, Adobe agrees to comply with all applicable equal opportunity laws including, if appropriate, the provisions of Executive Order 11246, as amended, Section 402 of the Vietnam Era Veterans Readjustment Assistance Act of 1974 (38 USC 4212), and Section 503 of the Rehabilitation Act of 1973, as amended, and the regulations at 41 CFR Parts 60-1 through 60-60, 60-250, and 60-741. The affirmative action clause and regulations contained in the preceding sentence shall be incorporated by reference.

Contents

Chapter 1: Introduction
ColdFusion and ColdFusion Builder documentation
ColdFusion and ColdFusion Builder learning resources
Chapter 2: About ColdFusion Builder
ColdFusion Builder configurations
Activating ColdFusion Builder
Updating ColdFusion Builder
Installing third-party Eclipse plug-ins
ColdFusion Builder Help System
Getting started with ColdFusion Builder
Chapter 3: ColdFusion Builder Workbench Basics
About the workbench 9
Workbench menus, toolbars, and keyboard shortcuts
About ColdFusion Builder perspectives
ColdFusion Builder Development perspective
ColdFusion Debugging perspective
Add views to the workbench
ColdFusion Builder editors
Customizing a perspective
Chapter 4: Code Editing in ColdFusion Builder
. CFML Editor
Code Assist
Code colorization
SQL Editor
Code folding and unfolding40
Syntax checking and highlighting41
Code refactoring
Tag wizard
Typing preferences
CFML Editor keyboard shortcuts
Chapter 5: Managing Servers
Understanding web server terminology
Adding ColdFusion servers
Using Servers View
Import RDS server settings
Chapter 6: Managing Projects
About projects
Creating a ColdFusion project
Configure properties for projects and servers

Contents

Add ColdFusion pages, interfaces, and components	56
Set URL Prefix	58
Import, export, and delete projects	58
Cloak projects and files	59
Link to resources outside the workspace	60
Deploy projects over FTP and Secure FTP connections	61
Import Ajax libraries	61
Working with Flash Builder projects	62
Developing AIR applications	62
Chapter 7: Debugging Applications	
Using ColdFusion debugger	64
Debugging your application	65
Debugging remote applications	69
Chapter 8: ColdFusion Builder Extensions	
About extensions	71
Developing extensions	71
Creating user interfaces for extensions	82
Specifying callback commands from handlers	84
Using the Extensions view	87
Use ColdFusion Builder Extension Creator to create and package extensions	88
Chapter 9: Using Extensions	
Adobe CFC Generator	90
AS Class Generator	92
Model-Glue Assistant	05

Chapter 1: Introduction

Adobe® ColdFusion® Builder™ is an integrated development environment (IDE) for developing Adobe® ColdFusion® applications.

There are various resources to help you get started and become proficient in using ColdFusion Builder. Depending on your background and what you want to accomplish with ColdFusion Builder, take a few minutes to read through the appropriate documentation resources.

New to ColdFusion

❖ It is most useful if you have basic ColdFusion experience before you start using ColdFusion Builder. You can start by viewing the Getting Started experience, which is available from the ColdFusion Administrator.

Experienced ColdFusion developers

ColdFusion Builder is built on Eclipse[™] (an open source IDE), so you must know specific terms and concepts to
effectively use it. If you are, however, familiar with working in an Eclipse-based environment, you will find that
ColdFusion Builder uses similar workbench conventions.

For more information, see "ColdFusion Builder Workbench Basics" on page 9.

- If you have developed code using a text editor in the past, you will find that ColdFusion Builder provides enhanced functionality that makes developing code much easier. For more information, see "About ColdFusion Builder" on page 3.
- For a quick overview of the features that are available with ColdFusion Builder, see "Getting started with ColdFusion Builder" on page 7.
- To successfully develop ColdFusion applications using ColdFusion Builder, use *CFML Reference* and *ColdFusion Developer Guide*. The *CFML Reference* contains detailed information on the CFML language elements and is available from the ColdFusion Builder Help system. For more information, see "Display CFML Reference Help" on page 6.
- For information about the complete documentation available for ColdFusion and ColdFusion Builder, see "ColdFusion and ColdFusion Builder documentation" on page 1.

ColdFusion and ColdFusion Builder documentation

All ColdFusion and ColdFusion Builder documentation is accessible from within ColdFusion Builder through the integrated Help system. For more information, see "ColdFusion Builder Help System" on page 4.

Go to the ColdFusion Help and Support pages at www.adobe.com/go/learn_cfu_support_en to view the online documentation.

In addition to viewing the documentation, you can also add and view comments to the documentation.

Adobe ColdFusion documentation

The ColdFusion documentation set includes the following titles:

Manual	Description
Installing Adobe® ColdFusion® 9	Describes system installation and basic configuration for Windows, Macintosh, Solaris, Linux, and AIX.
Adobe ColdFusion® 9 Administrator's Guide	Describes how to perform ColdFusion administration tasks such as managing server settings, configuring data sources and web servers, managing security, and deploying ColdFusion applications.
	This book also provides information about caching, setting up CFX tags, and monitoring server activity using the ColdFusion Server Monitor.
Developing Adobe® ColdFusion® 9 Applications	Describes how to develop your dynamic web applications. This book provides detailed information about using the CFML programming language and ColdFusion features, such as ColdFusion Web Services, ColdFusion Portlets, ColdFusion ORM, Ajax support, Flex and AIR integration, and integration with other products and technologies such as Microsoft Office, OpenOffice, and SharePoint.
Adobe® ColdFusion® 9 CFML Reference	Provides descriptions, syntax, usage, and code examples for all ColdFusion tags, functions, and variables.

Adobe ColdFusion Builder documentation

The ColdFusion Builder documentation set includes the following titles:

Manual	Description
Installing Adobe® ColdFusion® Builder	Describes ColdFusion Builder installation, as a standalone installation or as a set of plug-ins within an existing Eclipse workbench, for Windows and Macintosh platforms.
Using ColdFusion® Builder	Describes how to use ColdFusion Builder as an integrated development environment (IDE) for developing applications using ColdFusion.

ColdFusion and ColdFusion Builder learning resources

The following additional online resources are available for learning ColdFusion and ColdFusion Builder:

Resource	Link
ColdFusion Help and Support	www.adobe.com/go/learn_cfu_support_en
ColdFusion Developer Center	www.adobe.com/go/learn_cfu_cfdevcenter_en
Adobe ColdFusion online forums	www.adobe.com/go/learn_cfu_forums_en

Chapter 2: About ColdFusion Builder

Adobe® ColdFusion® Builder™ is built on top of Eclipse™, an open-source IDE (Integrated Development Environment). An IDE contains most of the tools that developers need within a single application. ColdFusion Builder provides tools for editing and validating code, managing files and projects, and debugging. The plug-in architecture of ColdFusion Builder lets you extend the functionality for your own needs.

ColdFusion Builder runs on Microsoft* Windows* and Apple* Macintosh platforms. The installation configuration options let you install ColdFusion Builder as a standalone installation or as a set of plug-ins within an existing Eclipse workbench installation. For more information, see *Installing Adobe ColdFusion Builder*.

ColdFusion Builder configurations

The ColdFusion Builder installer provides the following two configuration options:

Standalone ColdFusion Builder IDE Installation Installs ColdFusion Builder as a standalone IDE (Integrated Development Environment) built on Eclipse™ 3.5.1

ColdFusion Builder plug-ins within Eclipse IDE Installs ColdFusion Builder as a plug-in within an existing Eclipse or Adobe® Flash® Builder™ installation. This configuration is for users who already use the Eclipse workbench and want to add ColdFusion Builder plug-ins to their toolkit of Eclipse plug-ins.

Note: You must have Eclipse 3.4.2 or higher installed on your computer to install the plug-in configuration of ColdFusion Builder.

If you are not sure which configuration to use, follow these guidelines:

- If you already use and have Eclipse 3.4.2 or higher installed, select the plug-in configuration.
- If you do not have Eclipse 3.4.2 or higher installed, select the standalone configuration. This configuration also allows you to install other Eclipse plug-ins, so you can expand the scope of your development work in the future.

The two configurations provide the same functionality. However, some menu names and the ways to access the menu commands sometimes differ slightly in the plug-in configuration.

Activating ColdFusion Builder

When you start ColdFusion Builder, you are prompted to enter the product serial number. When you enter a valid product serial number, activation happens in the background the first time the software detects an Internet connection. For more information, visit the Adobe Product Activation Center at www.adobe.com/go/activation.

If you do not enter the product serial number when you start ColdFusion Builder, you can use the trial version of ColdFusion Builder for 60 days. Once the trial expires, you need to purchase a license to continue using ColdFusion Builder.

Managing ColdFusion Builder licenses

If you are a single-license user you can use ColdFusion Builder on up to two computers. To use your ColdFusion Builder license on a different computer than your original two computers, deactivate the ColdFusion Builder license on one of the two computers. After which, you can use it on another computer.

To deactivate the ColdFusion Builder license, select Help > Adobe ColdFusion Builder Deactivation.

Note: If you are uninstalling ColdFusion Builder, Adobe recommends that you first deactivate your license and then uninstall ColdFusion Builder.

Updating ColdFusion Builder

Updates to ColdFusion Builder can include changes to security or new product functionality. Adobe recommends that you periodically check and install the updates, when available.

- 1 In Adobe ColdFusion Builder, select Help > Adobe ColdFusion Builder Updates. If any new updates are available, ColdFusion Builder downloads and installs the updates.
- **2** For the updates to take effect, restart ColdFusion Builder (standalone configuration) or restart Eclipse (plug-in configuration).

Installing third-party Eclipse plug-ins

ColdFusion Builder provides integration with third-party Eclipse plug-ins that let you extend or customize your development environment. You can install the third-party Eclipse plug-ins on Windows and Mac OS X platforms.

- 1 In Adobe ColdFusion Builder, select Help > Install New Software.
- 2 Click Add.
- 3 Enter the name and URL of the plug-in to install. For example, to install Subclipse version 1.0, enter the following URL: http://subclipse.tigris.org/update 1.0.x
- **4** Select the plug-ins to Install.
- 5 Click Next and follow the instructions in the Install wizard.
- 6 Click Finish.

Note: To ensure that the plug-in installs correctly, add the Galileo Update Site URL http://download.eclipse.org/releases/galileo (or an equivalent Eclipse update site URL).

ColdFusion Builder Help System

While you work in ColdFusion Builder, you can display context-sensitive Help for specific user interface elements of the workbench (views and dialog boxes) and language-reference help for code elements.

Adobe Community Help Client

Adobe Community Help client (CHC) is an AIR application that displays help content for ColdFusion Builder. The Help content is served directly from the web. When you open the CHC for the first time, an Internet connection is needed. You can then download the Help content to your desktop to use and search offline.

To open and view the ColdFusion Builder Help system, select Help > ColdFusion Builder Help.

Use context-sensitive Help

- 1 Select a view, dialog box, or any other user interface element in the workbench.
- 2 Press F1 (Windows) to open the associated Help page in the Community Help Client.

To use context-sensitive Help on Mac OS, set a keyboard shortcut to the Dynamic Help command. To specify a keyboard shortcut for the Dynamic Help command, do the following:

- 1 Select Adobe ColdFusion Builder > Preferences.
- 2 In the tree view, select General > Keys.
- **3** Select the Dynamic Help command.
- 4 Press the key binding combination that you want to set. For example, to enter Ctrl+Shift+1, press and hold the keys Ctrl and Shift and then press 1. A plus sign (+) between the keys indicates that you must press the keys in succession.

Community Help Client Preferences

You can set CHC preferences to control the Help content display.

- 1 In the CHC, select Edit > Preferences.
- 2 In the Preferences dialog box, set the following options, as required.

General Settings

- You can select a light or dark theme for the CHC. A theme is a formatting choice that determines the appearance of the CHC. For example, when you apply a dark theme, the CHC has a dark background and theme-specific fonts.
- The CHC is launched as an AIR application, by default. You can, however, choose to launch the CHC in your web browser. To do so, select On (Launch Help In Browser).

Download Preferences

You can select the products and Help packages that you want to have available for offline use.

Updater Settings

CHC provides content updates and feature enhancements without reinstalling the AIR application. Select Notify Me When Updates Are Available to be prompted for new updates when you either open or close the CHC. You can also choose to manually search and install updates.

Local Content

You can manually delete the Help packages that you downloaded to your desktop.

Search and Filter options

CHC lets you search across different Help packages and search locations.

Click Search Options to display the following Search locations.

Local Help Searches the Help package downloaded to your desktop for offline viewing. Click Filter Results to narrow down your search results to a specific book in the Help package.

Adobe.com Searches up-to-date definitive reference content across all online resources available on adobe.com, including Developer Center articles, tutorials, and knowledgebase articles.

Community Help This search is cumulative of all the resources available on adobe.com as well as the most relevant content contributed by experts from the Adobe community.

Code Search The integrated code search lets you search through relevant code snippets available on adobe.com

Dynamic navigation

CHC provides dynamic navigation based on search results to find related content. All related content appears in the Related Topics tab.

Feedback and rating

You can comment on, rate, and contribute to Help content if you have a valid Adobe ID. If you do not have an Adobe ID, you can get one by registering yourself at https://www.adobe.com/membership.

Click Feedback And Rating in the bottom left-corner of the CHC, and provide your feedback. You can provide feedback in the form of a tip, example, or by suggesting a link to a relevant online resource.

Eclipse Help System

The Eclipse Help system displays CFML reference Help for code elements. The Eclipse Help system also displays Help for any third-party plug-ins that you install or that come packaged with ColdFusion Builder.

To open and view the Eclipse Help system, select Help > Help Contents.

Display CFML Reference Help

The *CFML Reference* is integrated into ColdFusion Builder, letting you quickly review the reference Help for a CFML tag or function.

- To open the Help topic for a CFML tag or function, do the following:
 - 1 In the CFML editor, select a CFML tag element or function by highlighting or placing the pointer on the built-in tag or function name.
 - 2 Press F1 (Windows) or the equivalent keyboard shortcut for Mac OS. A link to the Help page for the selected tag is displayed in the docked Help window.
 - **Note:** In Mac OS, when you press Command+Shift+/ to view Help for a CFML tag or function, generic editor Help appears in the docked Help window. To see the tag or function-specific Help, click the selected tag or function name in the CFML Editor again.
 - 3 Click the Help page link. The Help page for the selected tag or function is displayed.

Set Help Preferences

You can set Help preferences to control how Help is displayed in the Eclipse Help system.

- 1 In ColdFusion Builder, select Window > Preferences.
- 2 In the Preferences dialog box, you see a tree-view structure on the left side. Select Help.
- 3 Set the following options, as required.

Use External Browser Lets you display help in a web browser of your choice. By default, the embedded browser of the IDE displays Help. Select the Use External Browser check box and then select the Web Browser link to select your web browser.

Open Window Context Help Determines how to display context-sensitive Help links for an open window. By default, context-sensitive Help links are displayed in the Dynamic Help view which, when opened, is docked into the current perspective like all other views. To display context-sensitive Help links in an infopop (similar to a tooltip), select In An Infopop.

Open Dialog Context Help Determines how to display context-sensitive Help links for an open dialog box. By default, Help is displayed in the dialog box. To display context-sensitive Help links in an infopop (similar to a tooltip), select In An Infopop.

Open Help View Documents Determines where to display documents that are opened from links in Dynamic Help. By default, In-place is selected, and Help documents open in the Dynamic Help view window. To open Help documents in the ColdFusion Builder IDE editing area, select In-place.

Use dynamic Help

Dynamic Help is docked to the current perspective and displays topics for the associated views and dialog boxes.

❖ Select Help > Dynamic Help.

To change the default keyboard shortcut binding, select Window > Preferences > General > Keys, and change the associated binding for the Dynamic Help command. For more information on changing keyboard shortcuts, see "Keyboard shortcuts" on page 14.

Getting started with ColdFusion Builder

Using ColdFusion Builder, you can develop ColdFusion applications in a full-featured IDE that lets you complete the following tasks:

Note: Before getting started with the tasks, ensure that you are familiar with the ColdFusion Builder workbench and its capabilities and features. For more information, see "ColdFusion Builder Workbench Basics" on page 9.

- **Create ColdFusion projects**: Using the Project wizard, you can create a project and configure a local or remote server with it. For more information, see "Creating a ColdFusion project" on page 55.
- Add and manage servers: ColdFusion Builder includes integrated server management that allows you to manage your ColdFusion servers, the ColdFusion Administrator, and Server Monitor within ColdFusion Builder.
 - You can configure both JRun and non-JRun servers. To manage your applications efficiently, ColdFusion Builder provides features such as virtual hosts, virtual directories, and URL prefixes.
 - For more information on using these features and managing your servers, see "Managing Servers" on page 46.
- Deploy remote projects over FTP connection: ColdFusion Builder lets you manage both local and remote servers. The remote servers can be connected either through RDS (Remote Data Services) or FTP (File Transfer Protocol) connection. For more information about deploying and synchronizing remote projects over FTP connection, see "Deploy projects over FTP and Secure FTP connections" on page 61.
- Create ColdFusion pages, components, and interfaces: ColdFusion Builder provides wizards that let you create resources such as, ColdFusion pages, ColdFusion components (CFCs), and interfaces. You can associate these resources to a project. For more information, see "Add ColdFusion pages, interfaces, and components" on page 56.
- Write and edit your ColdFusion application source code using the CFML editor: ColdFusion Builder provides code editors to edit CFML, HTML, JavaScript, and CSS code. Based on the type of code that you are editing, the appropriate editor is opened. For more information, see "ColdFusion Builder editors" on page 30.
 - The editors provide many features, including code colorization, code assist, and Outline view, which help you navigate through your code.
 - The CFML editor provides features such as code completion, code refactoring, and streamlined code navigation. ColdFusion Builder lets you use different colors and fonts to display your code in the editor. For more information on the complete feature-functionality of the CFML Editor, see "Code Editing in ColdFusion Builder" on page 32.

- Write and edit SQL statements using the SQL Editor: The CFML editor has an integrated SQL editor that lets you edit and write SQL statements. You can also set code colorization preferences for supported SQL statements. For more information on the SQL Editor, see "SQL Editor" on page 38.
- Use and create CFML dictionaries: ColdFusion Builder provides built-in CFML dictionaries that assist you with CFML code completion. CFML dictionaries are supported for ColdFusion versions 7, 8 and 9. You can also create your own custom CFML dictionary. For more information about using and creating dictionaries, see "CFML Dictionaries" on page 37.
- **Use ColdFusion Builder development views:** ColdFusion Builder provides many views that let you develop your applications easily.

The RDS FileView lets you access and explore file systems on local and remote servers. The RDS DataView lets you access and explore local or remote data sources. For more information, see "RDS FileView and RDS DataView" on page 17.

You can also query data on a local or remote data servers using the RDS Query Viewer. For more information, see "RDS Query viewer" on page 18.

The Services Browser view lets you browse through CFCs and their methods within the server web root. You can access both local and remote CFCs and web services. For more information, see "Services Browser view" on page 21.

The Snippets view and Outline view let you reuse and streamline your code. For more information, see "Snippets view" on page 22 and "Outline view" on page 16.

For more information about all the development views, see "ColdFusion Builder Development perspective" on page 15.

• Use the ColdFusion debugger to debug applications: ColdFusion Builder provides an integrated debugger with debugging views, like the Debug view and the Breakpoints view, which let you debug your applications. For more information about these views, see "ColdFusion Debugging perspective" on page 24.

You can add breakpoints to your code, step into or over functions, and examine and evaluate expressions. You can debug files on both local and remote servers. For more information, see "Debugging Applications" on page 64.

The Problems view, TailView view, and Console view detect syntax, server, and compilation errors and display them.

Use and develop ColdFusion Builder extensions: Use the Extensions view to manage ColdFusion Builder
extensions.

You can develop extensions to generate code, design user interfaces, and perform basic CRUD (Create, Read, Update, and Delete) operations on the database. You can also develop extensions to perform custom actions such as opening files in the CFML Editor or inserting text in an open file. For more information about creating extensions, see "ColdFusion Builder Extensions" on page 71.

ColdFusion Builder provides the ColdFusion Builder Extension Creator to guide you through the process of creating and packaging extensions. For more information, see "Use ColdFusion Builder Extension Creator to create and package extensions" on page 88.

The following extensions come packaged with ColdFusion Builder.

- · Adobe CFC Generator
- · ActionScript Class Generator
- · Model-Glue Assistant

For more information on installing and using these extensions, see "Using Extensions" on page 90.

Chapter 3: ColdFusion Builder Workbench Basics

ColdFusion Builder is an Eclipse-based development environment that allows you to develop Adobe ColdFusion applications and run them on ColdFusion servers. You use it to develop ColdFusion applications using coding and debugging tools.

About the workbench

The ColdFusion Builder workbench is a full-featured environment for developing Adobe ColdFusion applications. Much of the basic functionality of the ColdFusion Builder IDE comes from Eclipse. The ColdFusion Builder plug-ins add features and functionality for creating ColdFusion applications. The plug-ins also provide tools for modifying the IDE user interface and supply some core functionality to support application building.

Workbench The workbench is the ColdFusion Builder development environment. The workbench contains three primary elements: *perspectives*, *editors*, and *views*. You use all three in various combinations at various points in the application development process. The workbench contains all the tools you use to develop applications.

Perspective A perspective is a group of views, editors, menus, and toolbars in the workbench. Essentially it is a special work environment that helps you accomplish a specific type of task. For example, ColdFusion Builder contains two perspectives. You use the ColdFusion Builder Development perspective to develop applications and the ColdFusion Debugging perspective to debug them.

For more information about perspectives, see "About ColdFusion Builder perspectives" on page 14.

Editor An editor allows you to edit various types of files. The editors available to you vary according to the number and types of Eclipse plug-ins installed. ColdFusion Builder contains editors for writing CFML, HTML, JavaScript, and Cascading Style Sheets (CSS) code. For more information about code editing in ColdFusion Builder, see "ColdFusion Builder editors" on page 30 and "Code Editing in ColdFusion Builder" on page 32.

Views A view typically supports an editor. For example, when you edit CFML, the Outline view and Snippet view are also displayed in the ColdFusion Builder Development perspective. These views support the development of ColdFusion applications and are therefore displayed when a CFML file is opened for editing.

Some views support the core functionality of the workbench itself. For example, the File Explorer view allows you to manage files and folders within the workbench. The RDS Dataview and RDS Fileview display data sources, files, and directories on both remote and local servers.

The term *view* is synonymous with the term *panel* as it is used in Adobe Dreamweaver* and other Adobe development tools.

For more information about the views in the ColdFusion Builder Development perspective, see "ColdFusion Builder Development perspective" on page 15.

For more information about the views in the ColdFusion Debugging perspective, see "ColdFusion Debugging perspective" on page 24.

Workspace Not to be confused with *workbench*, a *workspace* is a defined area of the file system. The workspace contains the resources (files and folders) that make up your application projects. A workspace can contain multiple

projects. You can work with only one workspace at a time; however, you can select a different workspace each time you start ColdFusion Builder. For more information, see "Managing Projects" on page 55.

Resource The general term *resource* applies to the files and folders in the projects in a workspace. For more information, see "Add ColdFusion pages, interfaces, and components" on page 56 and "Add other files" on page 58.

Project All the resources that make up your applications are contained within projects. You cannot build an application in ColdFusion Builder without first creating a project. For more information, see "Managing Projects" on page 55.

Workbench menus, toolbars, and keyboard shortcuts

You access workbench commands through the menu bar, right-click context menus, toolbars, and keyboard shortcuts.

Workbench menus

The ColdFusion Builder workbench contains the following main menus:

File menu

The File menu lets you create, save, close, print, import, and export workbench resources and exit the workbench.

Menu command	Description
New	Creates a resource. Before you create a ColdFusion component, interface, or page, ensure that you have created a project to store these resources.
Open File	Open a file for editing. You can also open files that are not in the workspace.
Close	Closes the active editor. You are prompted to save changes before the file closes.
Close All	Closes all open editors. You are prompted to save changes before the files close.
Save	Saves the content of the active editor
Save As	Lets you save the contents of the active editor in a different filename and location
Save All	Saves the contents of all open editors.
Revert	Replaces the contents of the active editor with the previously saved contents.
Move	Moves the currently selected resources to a different project
Rename	Lets you change the name of the selected resource
Refresh	Refreshes the resource with the contents in the file system
Convert Line Delimiters To	Lets you convert line delimiters to the operating system applicable to your development or deployment platform:
	Windows (default)
	• Unix
	• MacOS 9
Print	Prints the contents of the active editor
Switch Workspace	Opens the Workspace Launcher that lets you switch to a different workspace. When you switch to a different workspace, the workbench is restarted.

Menu command	Description
Restart	Restarts ColdFusion Builder
Import	Lets you import resources to the workbench using the Import wizard
Export	Lets you export resources from the workbench using the Export wizard
Properties	Displays the properties dialog box for the selected resource. The Properties For dialog box provides information about the path to the resource and the date of the last modification on the resource. It also provides information if the project's resources have inherited their encoding and line delimiters or if they are set to a particular value.
Recent File List	A list of the most recently accessed files in the workbench. You can open these files from the File menu by clicking the filename. You can control the number of files that must appear in this list using the Preferences dialog box.
Exit	Closes the open resources and exits the workbench

Navigate menu

The Navigate menu lets you locate and navigate through resources in your workbench.

Menu command	Description
Go Into	Lets you navigate within hierarchies of resources such that the selected resource is at the root. That is, when you select a folder within a project and select Go Into, only the selected folder (and artifacts within the folder) appear in the Navigation view.
	This command is useful in navigating through large-sized projects with complex hierarchies.
Go To	Lets you jump to a specific resource or display the hierarchy that appeared before the current display.
	For example, select the Go Into command for a resource, and then select Go To > Back. The Back command displays the same hierarchy from which you activated the Go Into command.
Open Declaration	Opens declaration for selected code element.
Quick Outline	Displays a quick view of the Outline view. A hierarchical view of the code structure of the page appears in a pop-up menu.
Open Resource	Lets you select a resource in the workspace and open it in an editor using the Open Resource dialog box
Show In	Lets you find and select the currently selected resource in another view. If an editor is active, these commands are used to select the resource that is currently being edited in another view.
Next	Lets you navigate to the next item in a list or table in the active view
Previous	Lets you navigate to the previous item in a list or table in the active view
Last Edit Location	Lets you jump to the last edit position in the active editor
Go To Line	Lets you jump to a specific line in the active editor
Back	Lets you move editor focus to a previously opened file.
Forward	Lets you return editor focus from the previous file.

Project menu

The Project menu lets you manage projects in the workbench.

Menu command	Description
Open Project	Opens the currently selected project. The selected project must be closed for this command to be available.
Close Project	Closes the currently open project]
Properties	Displays the project properties dialog box

Window menu

The Window menu lets you display, hide, and manage the various views, perspectives, and actions in the workbench.

Menu command	Description
New Window	Opens a new workbench window with the same perspective as the currently open perspective
New Editor	Opens an editor that is of the same type as the currently active editor
Open Perspective	Opens a new perspective in the workbench
Show View	Lets you select the views to display in the workbench
Customize Perspective	Lets you customize the currently selected perspective
Save Perspective As	Lets you save the currently selected perspective, creating your own customized perspective.
Reset Perspective	Lets you reset a customized perspective
Close Perspective	Closes the currently open perspective
Close All Perspectives	Closes all the open perspectives in the workbench
Navigation	Contains shortcuts to navigate between the views, perspectives, and editors in the workbench
Preferences	Lets you set you preferences for using the workbench. There are a number of preferences to configure the appearance of the workbench and the views and editors contained in the workbench.

Toolbars

Workbench toolbar

The workbench toolbar contains buttons for important and frequently used commands. These commands are also available from various ColdFusion Builder menus.



 $Work bench\ toolbar$


The following buttons appear in the workbench toolbar (shown left to right):

Button/command	Description
New	Displays a pop-up menu that displays all the types of projects and documents you can create.
Save	Saves the document that is open in the editor and currently selected
Print	Prints the document that is open in the editor and currently selected

Button/command	Description
New ColdFusion Project	Opens the wizard to create a ColdFusion project.
Open CFC	Lists all the CFCs that are available for projects displayed in the Navigator view.
Debug	Uses the project's currently open file to begin a debugging session. You can also select other application files in the project from the attached pop-up menu.
Run	Runs the project's currently open file. You can also select other application files in the project from the attached pop-up menu.
External Tools	Selects a custom launch configuration
Search	Searches for text strings and filename patterns for files in the project
Next Annotation	Allows you to select and move forward to code annotations
Previous Annotation	Allows you to select and move backward to code annotations
Last Edit Location	Takes you to the code element that you last edited in the currently open file.
Back To	Lets you move editor focus to a previously opened file.
Forward To	Lets you return editor focus from the previous file.

CFML Editor toolbar

The CFML Editor contains buttons that are user interface shortcuts to frequently used commands. These commands are also available from various ColdFusion Builder menus. Some buttons in the toolbar are shortcuts to frequently used code elements, and are context sensitive to the code that you enter in the CFML Editor.



CFML editor toolbar

Button/command	Description
Open Tag wizard	Opens the Tag wizard.
	For more information about using the Tag wizard, see "Tag wizard" on page 44.
Insert cfabort	Inserts the cfabort tag.
	This command is context sensitive to the script code.
Insert cfdump	Inserts the cfdump tag. This command is context sensitive to the script code.
Wrap in cfoutput	Wraps the selected code within the cfoutput tag.
	This command is context sensitive to the script code that you enter in the CFML Editor.
Insert cfset	Inserts the cfset tag.
Insert cfscript Block	Inserts a cfscript code block.
Wrap in cftry/cfcatch	Wraps the selected code within the cftry or cfcatch tag, depending on the code.
	This command is context sensitive to the script code.
Wrap in ##	Wraps the selected code within "#" marks.
Wrap/Unwrap in cfcomment	Comments or uncomments the selected code.
Wrap/Unwrap in /* */	Wraps or unwraps the selected code within ""/* */"" marks
Wrap in Single Quotes	Wraps the selected code within single quotation marks.

Button/command	Description
Wrap in Double Quotes	Wraps the selected within double quotation marks.
To Uppercase	Changes the text in the selected code to uppercase.
To Lowercase	Changes the text in the selected code to lowercase.

Keyboard shortcuts

Most of the functions that are available from the ColdFusion Builder menu are also available as keyboard shortcuts. To display the list of all available keyboard shortcuts:

❖ Select Help > Key Assist

Modify keyboard shortcuts

You can modify the existing keyboard shortcuts as follows:

- 1 In ColdFusion Builder, select Window > Preferences.
- 2 In the Preferences dialog box, you see a tree-view structure on the left side.
- **3** In the tree-view structure, select General > Keys.
- 4 Select the command and the associated key Binding that you want to modify. For example, the command Activate Editor is associated with the key binding F12.
- 5 Press the key binding combination that you want to set. For example, to enter Ctrl+Shift+F, press and hold the keys Ctrl and Shift and then press F. A plus sign (+) between the keys indicates that you must press the keys in succession.
- **6** Use the When drop-down list to change the default key binding context. The key binding context determines when you want the keyboard shortcut to be active.
- **7** To add a second key binding to the same keyboard shortcut, select the command and click Copy Command. You can then set a second key binding combination.
- **8** To restore the default key binding associated to a command, select the command that you modified and click Restore Command.
- 9 To delete a key binding associated to a command, select the command and click Unbind Command.
- 10 Click Apply or OK.

About ColdFusion Builder perspectives

A perspective is a group of editors and views that support the completion of a task. ColdFusion Builder contains two perspectives: the ColdFusion Builder Development perspective and the ColdFusion Builder Debugging perspective.

Open and switch perspectives

When you open a file that is associated with a particular perspective, ColdFusion Builder automatically opens that perspective. That is, perspectives change automatically to support the task at hand. For example, when you create a ColdFusion project, the workbench displays the Development perspective. Similarly, when you start a debugging session, ColdFusion Builder switches to the Debugging perspective.

By default, perspectives open in the same window. To open a perspective in a new window, do the following:

- 1 Select Window > Preferences
- **2** In the tree view structure, select General > Perspectives.
- 3 Under Open a New Perspective, select In The Same Window.

You can manually switch perspectives by doing one of the following:

- Select Window > Open Perspective > Other from the main menu.
- Use the perspective bar in the main workbench toolbar.

Eclipse provides many predefined perspectives. So, if you use the plug-in configuration of ColdFusion Builder, you sometimes have additional perspectives.

You can access the other Eclipse perspectives by doing one of the following:

- Select Window > Open Perspective > Other from the main menu.
- Click in the perspective bar in the main workbench toolbar and select Other.


Set a default perspective

- 1 Select Window > Preferences.
- 2 In the tree view structure, select General > Perspectives.
- 3 Under Available Perspectives, select the perspective that you want to set as the default, and click Make Default.
- 4 Click OK.

The default perspective has the word "default" in parentheses after the perspective name.

ColdFusion Builder Development perspective

You use the ColdFusion Builder Development perspective to create, edit, configure, and run ColdFusion applications in ColdFusion Builder. In addition, you can configure and manage local or remote ColdFusion servers.



ColdFusion perspective

A. Outline view B. RDS Dataview C. RDS Fileview D. Perspective Bar E. Navigator view F. File view G. Source view H. Servers view I. Default Browser view J. Console view K. TailView view L. Services Browser M. Extensions view N. Snippets view

The ColdFusion Builder Development perspective includes these views:


Outline view

The Outline view displays a hierarchy of elements in the file that is currently open in the editor. For example, it displays the functions in a CFC file and the tags in an HTML file.

You use Outline view to inspect and navigate the structure of your CFML, HTML, JavaScript, and CSS pages. If a page contains multiple code elements, you can use the Outline view to see a hierarchical view of the code structure of the page.

You can sort the elements in Outline view alphabetically or in the order of their definition in the page. You can choose to view all the code elements or view only specific code elements.

• The Outline view displays the structure of your CFML code. For example, each item in the Outline view can represent a CFML tag.



Outline view

- Double-click an element in Outline view to directly go to that element in the editor, instead of scrolling through the entire code. When you select an item in Outline view, that item is highlighted in the editor, which makes it easier to navigate your code.
- Use the filter to search for a tag or element in the Outline view. Enter the name of the tag or element to search for in the Filter field. The matching strings are displayed in the Outline view.

To specify the CFML tags to be displayed in an Outline view, select ColdFusion > Editor profiles > Editor > Outline. Then select, add, or remove tags, as required.

RDS FileView and RDS DataView

To use Remote Data Services (RDS), enable RDS while installing the ColdFusion server. ColdFusion Builder provides views to access files and data sources on a remote server.

The RDS FileView displays the files and directories on both remote and local servers. The RDS DataView displays the data sources configured in a remote server.

When you add a ColdFusion server instance in ColdFusion Builder, it automatically becomes available in RDS FileView and RDS DataView.

Configure a remote server for RDS FileView

If you want to configure a remote server manually and then access its files and directories using RDS FileView, do the following:

- 1 Click RDS FileView in the upper-right corner of the ColdFusion Builder perspective.
- 2 Right-click in RDS FileView and select RDS Configuration.
- 3 Click New.
- 4 Specify remote server information such as the host name, port number, user name, and password.
- 5 Select Prompt For Password.

- **6** Click Test Connection to check that the RDS configuration is correct. Then, click OK.
- 7 Select the remote server from RDS FileView.
- 8 Specify the password for the remote server to view its files and directories.

Configure a remote server for RDS DataView

To configure a remote sever and access data sources from the remote server using RDS DataView:

- 1 Click RDS DataView.
- 2 Right-click in RDS DataView and select RDS Configuration.
- 3 Click New.
- 4 Specify the server information such as host name, port number, remote server user name, and password.
- **5** Select Prompt for Password.
- **6** Click Test Connection to check that the RDS configuration is correct. Then, click OK.
- 7 Expand the new server in RDS DataView to view data sources.

RDS Query viewer


The RDS Query viewer lets you create and run queries on a selected data source.

The RDS Query Viewer is available in the RDS DataView toolbar. To create and execute a query using the RDS Query viewer, do the following:

- 1 Click in RDS DataView to open RDS Query Viewer area.
- **2** Type the query in the blank area.

You can also build a query by dragging tables and columns from the RDS DataView view into the RDS Query Viewer.

- **3** Select the server and data source from the drop-down list.
- 4 Click Execute Query. The results of the query are displayed in the RDS Query Viewer area.



RDS query viewer

Right-click a table in the RDS DataView view and select Show Table Contents. You can view all the records of the selected table in the RDS Query Viewer.

Navigator view

The Navigator view displays ColdFusion projects and other projects, and allows navigation through the project's files and folders.

File view

The File view displays files and directories on the local computer where ColdFusion Builder is installed and allows you to create new files.

If you edit a file outside ColdFusion Builder, you can automatically refresh the file in ColdFusion Builder. To do so, select Window > Preferences > General > Workspace, and select Refresh Automatically.

The File view also lets you add FTP sites and browse files on the FTP server. ColdFusion projects can be associated with FTP connections so that you can easily upload, download, and synchronize files. For more information, see "Deploy projects over FTP and Secure FTP connections" on page 61.

Servers view

Displays the details of ColdFusion servers including server name, status, description, server type, server host, and port. You can use the Server view to perform these tasks:

- Add and delete a ColdFusion server
- Start and stop a server

- · Launch Server Monitor
- Launch ColdFusion Server Administrator
- Open server log

For more information, see "Managing Servers" on page 46.

Source view and Default Browser view

The Source view displays the source code for files. The Default Browser View displays the output in an HTML or CFML page.

Console view


The Console view displays the status of the ColdFusion server and any messages from the ColdFusion server.

TailView view

The TailView view displays the Server log and Workspace log, and lets you easily navigate through the logs. To automatically display the logs, RDS must be configured and enabled.

After selecting a server, you can open logs from the shortcut in the button bar of the Server Manager. Select the log to open it in the TailView view. By default, the TailView view opens the Exception log. When you are in Server view, you can open the Exception log by right-clicking and selecting Open Log.

To manually open the logs, right-click in the TailView view and select Add. Browse to and select a log file on your computer's file system.



TailView view

The Tailview view toolbar contains the following buttons (left to right) that let you manage multiple logs in different tabs.



Button/command	Description
Move Left	Moves the Server log or Workspace log to the left
Move Right	Moves the Server log or Workspace log to the right
Adds Log	Opens a log file on your computer's file system
Starts Watching Log File	Starts watching on a log file
Stops Watching Log File	Stop watching on a log file
Reloads The Log File	Reloads a log file
Clears Log File In Display	Removes the log file displayed in the TailView view, without deleting it from the computer's file system
Erases Log File On Disk	Remove a log file from the computer's file system
Deletes Log Tab	Removes a log file from the computer's file system
Deletes All Log Tabs	Removes all the log tabs from the TailView view
Scroll Lock	Prevents the Console view from scrolling.
Color Settings	Sets color preferences for displaying the log file in the TailView view

Services Browser view

The Services Browser view lists the servers added in the Server Manager and lets you browse through ColdFusion components (CFCs), web services and their methods.

Browse ColdFusion components

The Services Browser view lists the following components:

- Components that the ColdFusion component browser lists. The ColdFusion component browser is located at *cf_root*/wwwroot/CFIDE/componentutils/componentdoc.cfm
- Components that are located in any directories specified in the ColdFusion Administrator Mappings page
- · Components that are located in any directories specified in the ColdFusion Administrator Custom Tag paths page

The Services Browser view toolbar contains the following buttons (left to right) that let you filter methods in CFCs based on the access type - remote, public, package, and private.



Services browser toolbar

Button/command	Description
Show System CFCs	A toggle button that shows or hides system CFCs. System CFCs are stored within the server web root.
Show Remote	A toggle button that shows or hides methods with the access type - remote
Show Public	A toggle button that shows or hides methods with the access type - public
Show Package	A toggle button that shows or hides methods with the access type - package
Show Private	A toggle button that shows or hides methods with the access type - private

Manage web services

The Services Browser view lets you manage a list of web services by adding or deleting WSDL URLs from a list.

- To view the list of web services, click **\(\)** in the Services Browser view.
- To add a web service to the list, click (1), enter a valid WSDL URL, and click OK.
- To delete a web service, select the web service, and click .

When you are editing a ColdFusion file, you can use the Services Browser view to generate CFML code to run a web service or to create a web service object. Similarly, when you are editing an ActionScript file, you can use the Services Browser to generate ActionScript.

To run or create a web service, do the following:

- 1 Place your pointer where you want to insert the code.
- **2** View the list of web services.
- 3 Highlight a web service or a method in a web service, right-click, and select:
 - Insert CFObject to insert a web service.
 - Insert CreateObject to create a web service.

Extensions view

You use the Extensions view to perform the following tasks:

- "Install and uninstall extensions" on page 87
- "Import and reload extensions" on page 88

The Extensions view also displays details like the extension name and description of the installed extension.

The Extensions view toolbar contains the following buttons (left to right) that let you manage extensions in the Extensions view.



Extensions view toolbar

Button/command	Description
Install Extension From Archive File	Lets you select the Archive file to install and opens the Extension Install wizard to guide you through the installation.
Import Extension From Folder	Lets you select the folder that contains the extension files.
Uninstall Selected Extension	Uninstalls the selected extension.
View Details About Selected Extension	Displays details about the selected extension.

Snippets view

A code snippet is a piece of text that you can insert and reuse in your files, without having to type the text each time. You use the ColdFusion Snippet view to create and save code snippets, variables, and plain text. You can add code snippets to an existing or new document.

The Snippet view toolbar contains the following buttons (left to right) that let you manage code snippets in the Snippets view.



Code snippet toolbar

Button/command	Description
Refresh Snippet View	Refreshes the Snippet view
Insert The Selected Snippet	Inserts the selected snippet into the document
Create A New Snippet	Creates a code snippet
Edit The Selected Snippet	Lets you modify the selected code snippet
Delete The Selected Snippet	Deletes the selected code snippet
Create A New Snippet Package	Creates a snippet package to which you can add code snippets
Delete Selected Snippet Package	Deletes the selected snippet package only if it is empty. You cannot delete a snippet package that contains snippets.

Create a code snippet

- 1 In the Code Snippet area, click .
- 2 In the New Snippet dialog box, specify the snippet name, and the start and end blocks of code.
- **3** Click OK to create the code snippet.

Insert a code snippet

- 1 Move the cursor to the desired insertion point.
- **2** Select the code snippet from the Code Snippet area.
- **3** Click in the Code Snippet toolbar.

If you select code in the editor, and then insert a snippet, the snippet is wrapped between the start and end block of the selected code. If you insert a snippet without selecting code in the editor, the snippet is inserted at the current caret position. *caret* is the marker in the CFML editor that indicates where the next character appears.

You can also edit or delete an existing code snippet or an entire code snippet package from the Code Snippet area.

Using trigger text to insert snippets

You can insert snippets in the CFML editor using trigger text. For example, you create a snippet and give it the trigger text "abc." To insert this snippet in the editor, you type abc and press Ctrl + J (Windows) or Command + J (Mac). The text abc is replaced with the associated snippet.

Specify the path to store snippets

Snippets are stored in a snippet's directory as an XML file. By default, snippets are stored in the workspace/.metadata/snippets directory of your project workspace. To specify a different directory, do the following:

- 1 From the Windows menu, select Preferences.
- 2 In the tree view structure of the Preferences dialog box, select ColdFusion > Snippets.
- **3** Specify the path to the directory in which to store snippets.

System-defined snippet variables

Snippet variables are case sensitive. The following system-defined variables are available.

Variable	Description
\$\${DATE}	The system date with the year as a four-digit number. For example, 12/01/2009
\$\${TIME}	The system time using a 12-hour clock. For example, 15:15:05 PM
\$\${DATETIME}	The system date and time. For example, 12/01/2009 15:15:05 PM
\$\${DAYOFWEEK}	The full name of the day of the week. For example, Monday
\$\${CURRENTFILE}	The filename of the currently open file. For example, application.cfm
\$\${CURRENTFOLDER}	The fully qualified path of the currently open folder. For example, C:\workspace\myproject
\$\${CURRENTPATH}	The fully qualified path of the currently open file. For example, C:\workspace\myproject\application.cfm
\$\${CURRENTPRJPATH}	The project name of the currently open project. For example, myproject
\$\${USERNAME}	The name of the current user.
\$\${MONTHNUMBER}	The month, from 01 through 12.
\$\${DAYOFMONTH}	The day of the month from 01 through 31.
\$\${DAYOFWEEKNUMBER}	The day of the week as a number, from 1 through 7. Sunday is considered as the start of ther week. So, for example, Monday is 2.
\$\${DATETIME24}	The date and time using a 24-hour clock. For example, 12/01/2009 15:30:00
\$\${YEAR}	The current year as a four-digit number. For example, 2009
\$\${YEAR2DIGIT}	The current year as a two-didgit number. For example, 09

For example, to insert the current date, use the following system-defined variable:

Date: \$\${DATE}


User-defined snippet variables

User-defined variables prompt you for the variable name and default value. For example, the following user-defined variable prompts you to enter the author's name:

Author name: \$\${Author}

ColdFusion Debugging perspective

The ColdFusion Debugging perspective contains tools to debug your ColdFusion applications. There are different views that let you add breakpoints to your code, step into or over functions in your code, and examine and evaluate expressions. The editor works with the debugging tools to locate and highlight lines of code that need correction.



 $ColdFusion\ Debugging\ perspective$

A. Variables view B. Debug output buffer view C. Breakpoints view D. Expressions view E. Outline view F. Debug view G. Edit view H. Servers view I. Console view J. Problems view K. TailView view

The ColdFusion Debugging perspective contains the following views:

Variables view

The Variables view toolbar contains the following buttons (left to right) that let you show the current variables, including the variable scope.



Variables view toolbar

Button/command	Description
Show Type Names	Displays the type of the variables
Show Logical Structure	This command is not supported in ColdFusion Builder
Collapse All	Collapses the information in the view to show only variable types

Debug Output Buffer view

The Debug Output Buffer contains two panes:

Browser Displays what appears in the browser during application execution. Specify the URL of the page that you want to debug.

Note: When you click the Home button, the URL that you specified as the Home Page URL in the Preferences dialog box (Window > Preferences > ColdFusion > Debug Settings) appears. For more information on editing the Debugger settings, see "Specify debugger settings in ColdFusion Builder" on page 65.

Server Output Buffer Displays the Debugger output in two views - source view and HTML view.

The Server Output Buffer pane displays an output only when the Debugger is suspended at breakpoint. The output that appears is only up to the suspended breakpoint.

Note: The Server Output Buffer displays the output even for a page that is executed using an external browser.

Breakpoints view

The Breakpoints view toolbar contains the following buttons (left to right) that let you manage breakpoints during a debugging session.




Breakpoint view toolbar

Button/command	Description
Remove Selected Breakpoints	Removes the selected breakpoint
Remove All Breakpoints	Removes all breakpoints
Show Breakpoints Supported by Selected Targets	Displays the breakpoints that you are currently debugging
Go to File for Breakpoint	Goes to the file in which the selected breakpoint is set
Skip All Breakpoints	Ignores all breakpoints
Expand All	Expands all the breakpoint information in the view
Collapse All	Collapses all the breakpoint information in the view
Link with Debug View	Highlights the selected breakpoint when the application stops execution in the Debug View
Add Java Exception Breakpoint	Lets you specify which Java exception to throw when you reach the selected breakpoint
Menu	Lets you specify the type of information to display in the Breakpoints view

Expressions view

The Expressions view lets you create expressions using variables and functions; you can inspect, evaluate, and watch these expressions. The Expressions view also lets you evaluate and watch variables that you selected in the Variables view.



Expressions view

The Expression view toolbar contains the following buttons (left to right) that let you create, evaluate, and watch expressions.



Expressions view toolbar

Button/command	Description
Show Type Names	Displays the type of the variables
Show Logical Structure	Displays the logical structure in the view
Collapse All	Collapses all expressions in the view
Create a New Watch Expression	Adds a watch expression
Remove Selected Expressions	Removes the selected variable or watch expression
Remove All Expressions	Removes all variables and watch expressions in the Expressions view

Outline view

The Outline view displays the current source file's content in outline form. For more information, see "Outline view" on page 16.

Debug View

The Debug view keeps the results of each debug session. The Debug view shows the stack trace when the page execution is suspended at breakpoint or when stepping into or over code.

The Debug toolbar contains the following buttons (left to right):



Debug toolbar

Button/command	Description
Resume	Resumes a debugging session
Suspend	Pauses a debugging session
Terminate	Stops a debugging session
Disconnect	Disconnects the debugger from the selected debug target when debugging remotely
Remove All Terminated Launches	Clears all terminated debug targets from the display
Step Into	Executes code line by line, including included code, UDFs, and CFCs
Step Over	Executes code line by line, excluding included code, UDFs, and CFCs
Step Return	Returns to the original page from which you entered the included code, UDF, or CFC
Drop to Frame	This command is not supported in ColdFusion Builder.
Use Step Filters/Step Debug	Ensures that all step functions apply step filters

Edit view

The Edit view displays the stacked source tabs, one tab for each source file that you have open.

Servers view

The Servers View lets you start, stop, and manage servers in ColdFusion Builder. You can also launch the ColdFusion Server Monitor and ColdFusion Server Administrator from the Servers View.




The Servers view toolbar contains the following buttons (left to right) that let you manage servers.

Button/command	Description
Add Server	Adds a server
Start Server	Starts a server
Restart Server	Stops and starts a server
Pause Server	Pauses the server
Stop Server	Stops a server
Open Console/Shell	Opens a new console and displays a pop-up menu to select other servers
Open Log	Opens the server log in the TailView view

For more information about managing servers and using Servers view, see "Using Servers View" on page 53.

Console view

Console view displays the output from trace statements placed in your CFML code and also feedback, like status, warnings, and errors from the debugger itself.



Console view

The Console view toolbar contains the following buttons (left to right) that let you view and manage the trace statements in the Console view.




Console toolbar

Button/command	Description
Clear Console	Clears all content from the Console view
Scroll Lock	Prevents the Console view from scrolling
Pin Console	Prevents the console from refreshing its contents when another process is selected
Display Selected Console	Displays the selected console
Open Console	Opens a new console and displays a pop-up menu to select other console views

Problems view

As you enter code, the ColdFusion Builder compiler detects syntax and other compilation errors, and displays the errors in the Problems view. The Problems view shows errors only for CFML files that are open in ColdFusion Builder.



TailView view

The TailView view displays the server logs. For more information, see "TailView view" on page 20.

Add views to the workbench

The workbench contains views besides the views associated with ColdFusion Builder's default development and debugging perspectives. These additional workbench views help you streamline the application development process.

❖ To add a view to the workbench, select Window > Show View > Other > General

These optional views are categorized by type and are associated with distinct workbench functionality or with specific Eclipse plug-ins.

Several workbench views, like the Tasks, Bookmarks, and Search views, are valuable aids as you develop your applications in ColdFusion Builder.

ColdFusion Builder editors

Editors are associated with resource types. As you open resources in the workbench, the appropriate editor is opened. The workbench is a document-centric (and project-centric) environment for developing applications.

Use the CFML editor to edit CFML files. For more information, see "Code Editing in ColdFusion Builder" on page 32.

Use the HTML editor to edit HTML code and the JavaScript editor to edit JavaScript code. The CSS editor lets you display and edit Cascading Style Sheets; you can then apply styles to the visual elements of your applications.

You can use the Link with Cursor feature to switch between the different editors based on the type of code you are editing. The editors provide many features, including code colorization, code assist, and Outline view, that help you navigate through your code and keep it valid.

As you enter CFML, HTML, JavaScript, and CSS code, hints are displayed to help you complete your code. This feature is called *Code Assist*. For more information, see "Code Assist" on page 33.

Customizing a perspective

You can configure the layout of your perspective; that is, you can configure the views and editors that are visible in the perspective. For example, you can configure the Tasks view to be visible in one perspective, and hidden in another perspective. You can also configure several other aspects of a perspective, such as the following:

- File > New submenu items
- Window > Perspective > Other submenu items
- Window > Other Views submenu items
- · Action sets (buttons and options) that appear in the toolbar and in the main menu

Note: Menu names differ slightly in the plug-in configuration of ColdFusion Builder.

Create a customized perspective

- 1 Open the perspective to modify.
- **2** Select Window > Customize Perspective.
- 3 Select the Shortcuts tab or the Commands Groups Availability tab, depending on the items that you want to add or remove in your customized perspective.

- **4** Use the check boxes to select the element that you want to be visible on menus and toolbars in the selected perspective.
- 5 Click OK.
- **6** Select Window > Save Perspective As.
- 7 In the Save Perspective As dialog box, enter a name for the modified perspective and click OK.

Note: When you save a modified perspective, ColdFusion Builder adds the name of the modified perspective to the Window > Open Perspective > Other menu.

Delete a customized perspective

You can only delete perspectives that you created. You cannot delete perspectives that are delivered with the workbench.

- 1 In ColdFusion Builder, select Window > Preferences.
- 2 In the Preferences dialog box, you see a tree-view structure on the left side.
- **3** In the tree-view structure, select General > Perspectives.
- 4 Under Available Perspectives, select the perspective that you want to delete.
- 5 Click Delete, and then click Yes to confirm the delete action.
- 6 Click OK.

Reset a customized perspective

After you have modified a perspective, you can restore it to its original layout.

- 1 In ColdFusion Builder, select Window > Preferences.
- 2 In the Preferences dialog box, you see a tree-view structure on the left side.
- **3** In the tree-view structure, select General > Perspectives.
- 4 Under Available Perspectives, select the modified perspective that you want to reset.
- **5** Click Reset, and then click OK.

Chapter 4: Code Editing in ColdFusion Builder

CFML Editor

ColdFusion Builder provides a CFML Editor that has feature-rich code editing capabilities for CFM, CFC, HTML, JavaScript, and CSS files. The CFML Editor assists you in writing code by including features like, code completion, and streamlined code navigation. The CFML Editor lets you use different colors and fonts to display your code in the workspace.

You can customize your development environment by setting editor profiles and preferences.

Editor profiles

An editor profile lets you group and save the following editor preferences under one profile.

- Code Assist
- Colors
- Keys
- Outline
- · Syntax Checking
- Typing

Editor profiles are useful when you have different editor preferences for various development needs. For example, you can select a set of preferences like Code Assist, code colorization, and keyboard shortcut preferences and save them under a single editor profile. You can apply all these settings at once by selecting the editor profile.

To create an editor profile, do the following:

- 1 Specify the different editor preferences that you want to set.
- 2 From the Window menu, select Preferences.
- 3 In the tree-view, select ColdFusion > Editor Profiles, and click Create New Profile.
- 4 Enter a name for the profile. The current editor preference values that you set are saved under this profile.

You can also modify default settings and save the modified settings as a new profile. Additionally, you can also import or export profiles.

By default, ColdFusion Builder provides three editor profiles:

- Default Sets the ColdFusion Builder default editor preferences
- Dreamweaver Sets editor preferences similar to Dreamweaver editor preferences
- CFEclipse Sets editor preferences similar to CFEclipse editor preferences

To select an editor profile, click the Active Profile drop-down list in the Editor Profiles dialog box, and select the profile.

Editor preferences

- 1 From the Window menu, select Preferences.
- **2** In the tree-view, select ColdFusion > Editor Profiles > Editor.

You can specify default filenames for the CFM and CFC files that you create. To remove any trailing whitespaces in the file, select Trim Spaces Before Saving Files.

You can also specify any text or boilerplate code that must appear, by default, in every CFM and CFC file. For example, suppose you want copyright information to appear in every CFC file that you create. In this case, you can specify the copyright text in the CFC tab under New File Settings.

The editor preferences that you can set include code assist, code colorization, keyboard shortcuts, outline view, syntax checking, and typing preferences.

Optimizing ColdFusion Builder performance

The preference options that you select affect the performance of ColdFusion Builder. For faster editor performance, you can apply preset editor preferences. Once you apply the preset settings, your current preference settings are lost permanently. To save your current preference settings, save the settings as an editor profile.

To apply preset editor preferences, click Optimize Editor Preferences. The following preference settings are applied:

Code Assist

The following options are deselected.

- Automatically Display Code Assist When Typing
- · Automatically Display SQL Code Assist When Typing
- · Automatically Insert A Single Proposal
- · Automatically Insert A Closing Tag

The following options are selected.

- · Append Space After Inserting Selection
- Automatically Insert Equal Sign (=)
- · Automatically Quote Attributes

Typing

- · Enable Auto-insertion is selected.
- All the Auto-insert Matching Character For options are deselected.
- · Auto-close Tags is selected as Never.

Code Assist

Note: Code Assist is also called Content Assist. These terms are used interchangeably.

Code Assist is designed to assist you with code completion. Depending on the code that you enter, hints relevant to complete the code appear. As you type the code in the CFML editor, Code Assist prompts you with a list of valid CFML tags, parameters, and attributes. These suggestions appear in a pop-up menu. If you have HTML, JavaScript, or CSS content within the CFML code, Code Assist displays code completion hints for this code as well. Double-click or press Enter, to insert the code completion hint in the CFML Editor.

Code Assist is also available for script-based syntax; for example, code hints appear for functions and components in the script syntax. When you import Ajax libraries into ColdFusion projects, Code Assist is available even for the JavaScript code.


Using Code Assist

Code hints appear whenever the framework or language (CFML, HTML, JavaScript, and CSS) provides options for you to complete the current expression. For example, if you type within a CFML tag, you are prompted with a list of all the attributes of that tag.

1 In a CFML page, begin entering a CFML tag by typing:

ccf

Relevant code hints are displayed as follows:



- Code hints
- 2 Navigate through the list of code hints using the Up Arrow and Down Arrow keys.
- **3** Select a code hint and press Enter. The selected tag is added to the editor.
- 4 As you continue to enter code, additional code hints are displayed. You can also press Ctrl+<Space> to display code hints while you enter a line of code.

The Smart Tag Assist feature of the CFML editor identifies if a tag attribute is already entered for a particular tag. If you have already entered a tag attribute, that attribute does not appear in the list of suggested attributes.

Code Assist for CFM pages

- Displays methods and component list when you use the <cfinvoke> tag in a CFM file.
- Displays a drop-down list of predefined attributes and values when you press <cf+Ctrl+<space>.
- Displays a list of components (CFC) that can be loaded using createobject() or the <cfobject> tag.
- Displays methods created in a CFC, which can be called using the component object created in a CFM. Also displays a list of methods of all extended CFC files.
- Displays a drop-down list of all built-in and user-defined functions.

- Provides a list of variables, like, struct, array, query. These variables are declared in a page. The variables also appear
 as Code Assist for attribute values.
- Displays all the queries created using <cfquery> or queryNew(). To view the recordset, type <cfoutput query="">, and press Enter. or use *queryname*. (that is, query name followed by dot).
- Includes the functions, variables, tags, and queries from another CFM page once it is included in the current CFM page using the <cfinclude> tag.
- Allows you to browse and select a file as the input value for an attribute of CFM tags. CFM tags that require a file as the input value include <cfinclude>, <cfimage>, <cfdirectory>, <cfpdf>, <cffile>, <cfzip>, <cfspreadsheet>, and <cfcollection>.

Code Assist for CFC pages

- Displays a list of components (CFC) that can be loaded using createobject().
- Displays a list of components (CFC) that can be loaded using the <cfobject> tag.
- Displays methods created in a CFC, which can be called using the component object created in a CFM.

Examples:

```
• <cfset obj1 = createobject("component", "c1")>
        <cfset x = obj1.method1()>
• <cfset obj2 = createobject("component", "c2").init()>
• <cfset obj3 = new "c3"().method3()>
• <cfinvoke component="c4" method="method4">
```

- Displays a list of methods of all extended CFC files. The "extends" and "implements" keyword/attribute lists the available components and interfaces.
- Displays a list of components that can be extended in the current CFC file.

Note: Code Assist is not supported for comments that are added to component properties. For example, Code Assist is not supported for a comment that you add to the numeric accountID property as follows:/** @ -- code assist is not supported here --*/

- Displays a list of interfaces that can be used in a CFC with the implement keyword.
- Allows you to browse and select a file as the input value for an attribute of CFM tags or functions like <cfif fileexists()>.

CFM tags that require a file as the input value include <cfinclude>, <cfimage>, <cfdirectory>, <cfpdf>, <cffile>, <cfzip>, <cfspreadsheet>, and <cfcollection>.

Code Assist for scoped variables using variable mapping

Many ColdFusion frameworks create CFCs during application startup and store these CFCs as scope variables. To provide Code Assist for such CFCs, ColdFusion Builder must determine the content and data type (fully qualified name of the CFC).

To enable Code Assist for CFCs that are stored in scoped variables, define a project-level mapping for the variable name and its corresponding CFC type. ColdFusion Builder uses this mapping information and displays a list of CFC methods for the mapped variable, without creating an object of that data type. For example, you can map mycfc1 to com.adobe.mycfcs.cfc1. When you type mycfc1 and press Ctrl+<space>, all the methods available for com.adobe.mycfcs.cfc1 appear.

To configure a variable mapping, in the Properties dialog box, Specify the variable to map as mycfc1 and the mapped to value as com.adobe.mycfcs.cfc1. For more information, see "Configure variable mappings" on page 56.

Code Assist for ColdFusion ORM

Object Relational Mapping (ORM) is a programming technique that lets you define a mapping strategy using object models. You can use Object Relational Mapping to store and retrieve data from a relational database.

ColdFusion Builder provides Code Assist for the following ColdFusion ORM settings:

- Entity names in entityLoad, entityNew, and entityFindByPK functions.
- Methods and properties returned by entityLoad, entityNew, and entityFindByPK functions.
- Code hyperlinks for entity names and methods.
- Data sources in application.cfc. For example, <cfset this.datasource = >.
- Table attribute of the cfcomponent tag.

For more information about using ColdFusion ORM, see ColdFusion ORM in the ColdFusion Developer Guide.

Code Assist for Application.cfm and Application.cfc files

Code Assist is available for Application.cfm and Application.cfc files.

Application.cfm is considered an included file and Code Assist is available for all variables and functions within the file.

For Application.cfc, Code Assist is available only for scoped variables that are declared in onApplicationStart.

Set CFML Editor Code Assist preferences

- 1 From the Window menu, select Preferences.
- 2 In the tree-view, select ColdFusion > Editor profiles > Editor > Code Assist.
 - You can select the Code Assist Dictionary version to assist with code completion. ColdFusion 9, ColdFusion 8, and ColdFusion MX7 dictionary versions are supported.
 - Select the Automatically Display Code Assist When Typing check box to automatically display Code Assist when typing.

Note: When editing large-sized files, you can deselect the Automatically Display Code Assist When Typing check box to improve performance of the editor. You can, however, display code hints while you enter a line of code by pressing Ctrl+<Space> or any other keyboard shortcut that is set.

· You can choose to automatically quote attributes and select closing tags.

Code hyperlinks for CFCs and UDFs

Component names and UDFs are hyperlinked on Ctrl+hover. If you click the hyperlink, the corresponding code is opened in ColdFusion Builder. Code hyperlinks are available for:

- UDFs: local, included, and cfc.udfName
- Template in <cfinclude template="">
- CFCs in createobject(), <cfobject>, <cfinvoke>, new keyword, and extends attribute.

CFC name resolution using server mapping

Use ColdFusion Administrator to define server mapping for CFCs. The server mappings allow you to view these CFCs as part of Code Assist when you use the extend or implement keywords.

ColdFusion server mappings let cfobject and cfinvoke tags, or functions like createObject or new, access pages and find ColdFusion components outside the document root.

If you specify a path in these tags that starts with the mapping's logical path, ColdFusion looks for the CFC using the mapping's directory path. You can define server mapping for the CFCs using the ColdFusion Administrator. After mapping, you can view the CFCs in Code Assist when you use the extend or implement keywords, and component or method attributes. The CFCs suggested in Code Assist are resolved with their fully qualified names.

Once mappings are created for the CFC name resolution from the server, the server settings are cached and available even when the server is not running. The server settings are collected when the server is started or refreshed from ColdFusion Builder.

Specify server settings

- 1 From the Windows menu, select Preferences.
- 2 In the tree view structure, select ColdFusion > Server Settings.
- 3 Select the Build Server Settings check box and the Required check box to indicate the action for collecting server settings. For example, to collect server settings each time you start ColdFusion Builder, select the ColdFusion Builder Started check box.

CFML Dictionaries

ColdFusion Builder provides in-built dictionaries that assist you with CFML code completion. The CFML dictionary is an XML file that contains information about each tag and function contained in the library. For example, the CF9 dictionary file (cf9.xml) contains information about all the available CF9 tags and functions.

ColdFusion Builder provides dictionary support for ColdFusion 9, ColdFusion 8, and ColdFusion MX7 versions.

To select a dictionary version, do the following:

- 1 From the Window menu, select Preferences.
- 2 In the tree-view, select ColdFusion > Editor profiles > Editor > Code Assist.
- 3 Select the Code Assist Dictionary version drop-down list and select a dictionary version to assist with code completion.
- 4 Click Reload Dictionaries to reload all the dictionaries, including custom dictionaries.

Create custom CFML dictionaries

You can create a custom CFML dictionary (XML file) and make it available to use for Code Assist and Tag wizard within ColdFusion Builder.

- 1 Within the ColdFusion Builder installation, navigate to the following location:
 - \plugins\com.adobe.ide.coldfusion.dictionary XXX\dictionary
- **2** Create a folder called "Custom" within the Dictionary directory.
- 3 Create an XML file to describe the custom tags and functions.

For example, in the XML file, you describe each tag within <tag></tag> elements, and enclose all the tag elements within <dictionary></dictionary> elements as follows:

See the cf9.xml or cf8.xml files as reference to create the custom CFML dictionary.

Code colorization

ColdFusion Builder can highlight the syntax for CFML tag names, attributes, attribute values, keywords, comments, and various other elements in different colors. Code colorization is also supported in script-style coding. You can customize the color preferences and override the default Eclipse editor color preferences.

Set CFML Editor color preferences

- 1 From the Window menu, select Preferences.
- 2 In the tree-view, select ColdFusion > Editor profiles > Editor > Colors.
 - You can import and export your color preferences as a COL file.
 - You can specify color preferences for Tokens. Tokens include language preferences, errors, identifiers, keywords, literals, punctuators, and tags.
 - You can specify color preferences for specific regions of your code. You can specify a region between the start and end of code elements, and define a distinguishing color for that region.

Set SQL Editor color preferences

- 1 From the Window menu, select Preferences.
- 2 In the tree-view, select ColdFusion > Editor profiles > Editor > Colors. Under Tokens, scroll down to SQL, and select color preferences for comments, keywords, and text.

SQL Editor

The CFML editor has an integrated SQL editor that lets you edit, write, and execute SQL statements.

To use the SQL editor, you must have a server configured and running in ColdFusion Builder. The SQL editor does not support offline databases.

The SQL Editor supports Code Assist and code colorization for the following types of SQL statements:

Select

- Insert
- Update
- Delete

Note: For SQL statements within the cfquery tag, Code Assist is available in the CFML Editor itself. You need not open the SQL Editor for code completion hints.

Using SQL Editor

- 1 Do one of the following:
 - · Right-click in the CFML editor, and select SQL Editor.
 - Use the keyboard shortcut Ctrl+Alt+S (Windows) or Command_Alt+S (Mac OS).
- 2 In the SQL Editor, select a server from the Server drop-down list and a database from the Datasources drop-down list.
- **3** Enter the SQL statement and do the following:
 - Click Execute Query to display the results of the SQL statement in the Query Result tab. You can execute only SELECT statements in the SQL Editor.
 - Click OK to insert the SQL statement in the CFML editor at the current caret position. *caret* is the marker in the CFML editor that indicates where the next character appears.
- **4** You can also copy SQL code blocks from the SQL Editor directly into the CFML editor by selecting the code block and pressing Shift+Enter.
- **5** To edit a SQL code block in the CFML editor, select the code block, right-click, and select SQL Editor. The selected code block appears in the SQL Editor.

For more information about basic SQL syntax and writing SQL statements, see Using SQLin the ColdFusion Developer Guide.

SQL Code Assist

SQL Code Assist is available only for database table names and field names in the SQL statement.

By default, SQL Code Assist is turned on in ColdFusion Builder, and code hints for SQL statements are automatically displayed in the CFML Editor. To turn off the automatic display of SQL Code Assist, do the following:

- 1 From the Window menu, select Preferences.
- 2 In the tree-view, select ColdFusion > Editor profiles > Editor > Code Assist.
- 3 Deselect Automatically Display SQL Code Assist When Typing.

Even with the automatic display of SQL Code Assist turned off, you can still get code hints within your SQL statements as follows:

- 1 Begin entering the SQL statement in the SQL editor and press Ctrl+<Space> to display the database table names or field names.
- 2 Navigate through the list of table names or field names using the Up Arrow and Down Arrow keys.
- 3 Select a table name or field name and press Enter. The selected table or field is added to the SQL statement.

ColdFusion Builder provides Code Assist for the query attribute of the <cfoutput> tag. For example, when you type, <cfoutput query="">, and press Ctrl+<Space> with the caret position between the double quotes "". A list of queries created in that file or included files appears.

Code Assist is also provided for query names that are used in expressions.

For example, if you create a query like:

```
<cfquery datasource="dsn1"name="q1">
Select id, firstName, lastName from employee
</cfquery>
```

When you type the expression <cfset name = q1.> and press Ctrl+<Space>, ColdFusion Builder displays the columns selected in that SQL query.

SQL Code colorization

In the CFML editor, SQL code colorization is supported only within the cfquery tag. You can colorize SQL keywords, comments, and text within the cfquery tag. Colorization is supported only for the following types of SQL comments:

- /* */
- --

To set SQL code colorization preferences, see "Set SQL Editor color preferences" on page 38.

Code folding and unfolding

The CFML editor provides many shortcuts for navigating through your code. Shortcuts include folding and unfolding code blocks, opening the source of code definitions, and browsing and opening types. You can collapse and expand multiline code blocks to navigate, view, and manage complex code documents. In ColdFusion Builder, collapsing and expanding multiline code statements is called code folding and unfolding. You can use this feature in a CFM, CFC, or HTML file.

1 In the CFML Editor, click the fold icon (-) or the unfold icon (+) in the left margin of the editor.

Folding a code block hides all but the first line of code.

Move the pointer over the unfold icon (+) to show the folded code in a tool tip.

Unfold a code block to make the code visible

2 By default, all the lines of code are expanded. To fold or collapse all the lines of code except the first line, right-click in the left margin of the editor. Then select Folding > Collapse All.

Syntax checking and highlighting

When you select a tag or code bracket in a CFM file, the matching pair of the tag or bracket is automatically highlighted.


If you type code that is not recognized as valid CFML code, you are notified in the following ways:

• A cross-mark appears next to the line of code as follows:

Syntax problem highlighted

Hovering your pointer on the cross-mark gives more details about the error.

• The Problems view lists the error as follows:



Syntax problem displayed in Problems view

Each message contains a brief description of the error, the file and folder in which the error occurs, and its line number in the file. When you double-click the error, the file is opened in the editor and the line of code is highlighted.

Note: Syntax errors are displayed only for open CFM files and are not displayed after you close a CFM file.

Depending on the nature and severity of the errors, your application sometimes does not run properly until the errors are corrected.

Syntax checking preferences

- 1 From the Window menu, select Preferences.
- 2 In the tree-view, select ColdFusion > Editor Profiles > Editor > Syntax Checking.
- 3 Syntax checking is turned on by default. To turn off syntax checking, deselect Enable Syntax Checking.
- **4** To display syntax errors only when opening or saving a file, select Display Syntax Errors Only on File Save. While editing the file, all errors in the file are removed from the Problems view.

Code refactoring

Code refactoring is the process of improving the source code of a program without changing the overall result. Generally, code refactoring improves code readability and maintainability.

ColdFusion Builder supports various refactoring techniques like renaming, searching, and previewing of CFCs, CFMs, and UDFs at the project and workspace levels.

Refactor CFC or CFM filenames

When you rename a CFC or CFM, you can refactor all valid instances of the CFM or CFC, including all references to the CFM or CFC.

- 1 Right-click the file in the Navigator pane.
- 2 Select Refactor > Rename.

- **3** Enter the new name and preview the changes. When you preview the changes, you can review the selected instances and deselect any instance that you do not want to rename.
- 4 To rename CFCs or CFMs across all projects in the workspace, select Update All Projects In The Workspaces.

Note: You cannot rename a CFC or CFM in HTTP or Web server URLs unless the server is registered and running.

To undo refactoring, use the keyboard shortcut Ctrl+Z (Windows) or Command+Z (Mac).

Refactor UDFs in CFC or CFM files

- 1 Open the CFM or CFC file in the editor.
- 2 Point to the function name, right-click, and select Refactor > Rename
- **3** Specify the UDF name and click OK.

Note: Currently, function renaming is supported only through the main function declaration and not from function calls

Notes and considerations

- The location of a CFM or CFC file cannot be changed although the inherent Eclipse editor provides the capability to move files using the Move option.
- The CFML Editor does not support renaming a folder although Eclipse provides this option.

Refactoring methods

You can refactor methods created for application variables by creating variable mappings.

For example, consider a scenario where an application variable is defined for a CFC object as follows:

```
<cfset Application.appVar = createObject("component", "abc.AppCFM.a") >
```

Say, you have a CFC function, Method(), that you call as follows:

```
<cfset Application.appVar.Method()>
```

To refactor the Method() function, create a variable mapping for the application variable Application.appVar as follows:

- 1 In the Navigator view, right-click the project and select Properties.
- 2 In the Properties dialog box, select ColdFusion Variable Mappings.
- 3 Click New, enter the following details in the Add Mappings dialog box:
 - Variable Name: Application.appVar
 - Mapped To: abc.AppCFM.a

Reference search

You can search for a CFC, CFM, or UDF in a project or workspace.

- 1 Right-click the project in the Navigator pane.
- 2 Click References and select Project or Workspace. The results are displayed in the Search window in ColdFusion Builder.

Other than searching for references at the project or workspace level, you can search for references while working in the CFML code editor. Right-click in the CFML editor and select References > File to search for file references. You can also search for references at the project and workspace level from within the CFML editor.

Tag wizard

The Tag wizard assists you in adding tags and their attributes, even if you are not familiar with CFML. To use the Tag wizard in ColdFusion Builder, do the following:

- 1 Click the CFML tab in the Source area, if it is not already open.
- 2 Click the Tag wizard icon from the CFML toolbar. You can also open the Tag wizard by pressing the Ctrl+T.
- 3 If you do not know the tag, then search for the tag using the Tag wizard dialog box.
- 4 Specify the values for the tag attributes. The Tag wizard also displays values specific to an action attribute.
- 5 Click OK to add the tag to a CFML page.

Note: The Tag wizard is context sensitive, so you can edit a tag by moving the cursor to the tag and pressing Ctrl+T. The Tag wizard for that tag is displayed, and you can specify or change the tag attributes.

Typing preferences

When typing CFML tags, you can customize your typing preferences. You can specify preferences like the following:

- Auto-insert closing tags and matching characters (like, quotes and curly brackets)
- Auto-indent child tags on pressing Enter
- · Auto-change the matching tag when you modify a pair tag
- · Auto-suggest single quote and double quote when you quote attributes

Set CFML Editor typing preferences

Auto-insertion is enabled, by default. You can auto-insert matching characters for single and double quotes, brackets, and the '#' sign.

To turn off auto-insertion, do the following:

- 1 From the Window menu, select Preferences.
- 2 In the tree-view, select ColdFusion > Editor Profiles > Editor > Typing.
- 3 Deselect Enable Auto-insertion.

CFML Editor keyboard shortcuts

The CFML Editor lets you modify the default keyboard shortcuts and specify your own keyboard shortcuts. The default key shortcuts use Eclipse Key Bindings.

Set CFML Editor keyboard shortcut preferences

To modify a key binding, do the following:

- 1 From the Window menu, select Preferences.
- **2** In the tree-view, select ColdFusion > Editor profiles > Editor > Keys.
- 3 Select the Key Binding that you want to modify.
- 4 Under Edit Key Bindings, click to highlight the key binding.
- **5** Press the key binding combination that you want to set. For example, to enter Ctrl+Shift+1, press and hold the keys Ctrl and Shift and then press 1. A plus sign (+) between the keys indicates that you must press the keys in succession.

Chapter 5: Managing Servers

The comprehensive Server Management feature of ColdFusion Builder lets you start, stop, and restart the ColdFusion server, and access the ColdFusion Administrator and Server Monitor from a single Servers view. For more information about the Servers view, see "Using Servers View" on page 53.

You add a server, and associate it with a project to debug or preview files in the project. You also associate a server with a project to install and run the extensions that are packaged with ColdFusion Builder. For more information about adding servers, see "Adding ColdFusion servers" on page 47.

Understanding web server terminology

Before you set up and manage your server, read through the following topics to understand web server terms and concepts that are used in the documentation.

For detailed information about web servers and configuring them for ColdFusion, see Web Server Management in the ColdFusion Administrator's Guide

Document root

The term *Document Root* refers to a file system directory, from where your web server serves web pages. The term can vary from server to server, but the same concepts apply to most web servers.

URL prefix

A URL prefix maps a local file system resource with a URL.

In ColdFusion Builder, you use a URL prefix to preview or debug projects outside your web root or document root.

You can specify a URL prefix while creating a server, or by editing settings for an existing server. For more information, see "URL Prefix" on page 48.

You can also specify a URL prefix to an existing project or folder. For more information, see "Set URL Prefix" on page 58.

Usage Scenario

You have a project called "Project1". Project1 is configured to server1, whose document root is at C:\server1\MyDocs and URL is http://www.example1.com. Within Project1, you have a linked folder called "xyz". The folder xyz points to the document root of server2, which is C:\server2\MyDocs and the URL to access it is http://www.example2.com. You want to preview all the files within the xyz linked folder in ColdFusion Builder.

In this scenario, to preview files within the xyz linked folder, you create a URL prefix. You create a URL prefix by specifying the following details:

- Absolute path: C:\server2\MyDocs\
- URL to access the xyz folder: http://www.example2.com

Virtual host

The term *Virtual Host* refers to the method of hosting multiple websites (domain names) on a single web server. The multiple websites are differentiated by their apparent host names. For example, you can run websites www.example1.com, www.example2.com, and www.example3.com, on a single IP address.

In the ColdFusion Builder context, you can use a single ColdFusion server to run multiple websites that are configured as virtual hosts on an external web server like IIS or Apache.

For information on how to configure virtual hosts in the web server, see the web server- specific documentation.

When you associate a project with a virtual host, ColdFusion Builder functionality like, previewing, debugging, Content Assist, and building extensions, is extended to all the folders and subfolders within the project.

Virtual directory

The term *Virtual Directory* refers to a folder that is not physically contained in the document root although it is accessible through the server URL. To create a virtual directory, you specify an alias for the folder's path in the URL. The alias name is used to access resources within the folder.

Suppose the document root for your website (www.example.com) is c:\xyz\docs, and the folder that provides contents to your website is at d:\abc\content. Then, you define an alias for this folder called content. You can then access the website using the URL: http://www.example.com/content/

Adding ColdFusion servers

You add a ColdFusion server to test projects or applications that you create in the ColdFusion Builder workspace. The ColdFusion server can be a development server for testing and running your applications before you deploy them on a production server. You can add a local or remote ColdFusion server.

Add a local server

In the Servers view, do one of the following:

- · Right-click and select Add Server.
- Click 🖺.

Enter the following details in the ColdFusion Server Setup wizard:

General Settings

- Server Name: ColdFusion server name.
- Description: (optional) Description of the server.
- Application Server: Select the drop-down list and select JRun or select Other to configure a non-Jrun server.

Note: You cannot start, stop, or restart a non-JRun server within ColdFusion Builder.

- Host Name: Name of the ColdFusion server host. For example, localhost or 127.0.0.1.
- · Select Is Local.

Other Settings

- Webserver Port: Specify the port number of the ColdFusion server instance you are configuring. The default port number of the ColdFusion server is 8500.
- Context root: (applicable only for JRun servers with J2EE configuration) Enter the context root. The J2EE environment supports multiple, isolated web applications running in a server instance. Hence, J2EE web applications running in a server are each rooted at a unique base URL, called a context root (or context path).
- Application Server Name: (applicable only for JRun servers with J2EE configuration) Name of the JRun Server on which ColdFusion is deployed.
- RDS User Name: (optional) If you are using RDS, specify the RDS user name.
- RDS Password: (optional) Specify the RDS password.
 - **Note:** You set the RDS password in the ColdFusion Administrator. Do not confuse the RDS password with the ColdFusion Administrator password, which is also managed through the ColdFusion Administrator.
- Select Enable SSL to enable SSL support in ColdFusion Builder. Servers registered in the Server Manager can communicate using SSL.
- Select Auto Start and Auto Stop to automatically start and stop the ColdFusion server every time you launch and exit ColdFusion Builder.

Click Next.

Local Server Settings

Select the Local Server Settings tab, and specify the following local server settings, as applicable.

- Server Home: (applicable only for JRun servers) Browse and select the ColdFusion Server home directory. For example, C:\ColdFusion9 for a standalone ColdFusion server instance. For a multiserver instance, the server home is the Application Server Home directory, for example, C:\JRun4 for a JRun-J2EE or multiserver configuration.
- Document Root: Browse and select the web root location. If ColdFusion is configured with a web server, say IIS, then select the document root of the web server; for example, c:\inetpub\wwwroot.
 - This setting is required for previewing, debugging, and CFC name resolution in ColdFusion Builder.
- Version: (applicable only for JRun servers running on Windows) Select the ColdFusion server version from the Version drop-down list.
- Windows Service: (applicable only for JRun servers running on Windows) The Windows Service option is available only for standalone and multi-server configurations, and not J2EE configuration. If you want to start and stop the ColdFusion server using the Windows Service, select Use Windows Service To Start/Stop Server.

URL Prefix

(optional)

Note: You don't necessarily have to specify a URL when creating a server. You can specify a URL prefix even after creating the server by editing the server settings in the Servers view. You can also specify a URL prefix to an existing project or folder; for more information, see "Set URL Prefix" on page 58.

Select the URL Prefix tab and enter the following details:

- 1 Local Path: Browse to or enter the path to the local file system resource.
- **2** URL prefix: Enter the URL prefix.
- 3 Click Add.

Virtual Host Settings

(optional)

Note: When you specify a virtual host or virtual directory in ColdFusion Builder, corresponding settings must be specified in the configured web server. ColdFusion Builder does not validate these settings. So, if the settings in the web server are different from what you specify in ColdFusion Builder, ColdFusion Builder does not give an error.

To configure a virtual host, select the Virtual Host Settings tab, and do the following:

- 1 Click New and enter the following details in Virtual Host Settings section.
 - a Name: Specify a name for the virtual host. For example, vh1.
 - **Note:** You can provide any name and not necessarily the name that you provide in the web server.
 - **b** Host Name: The virtual host name as specified in your IIS or Apache web server settings. For example, www.example1.com
 - When you create a virtual host in ColdFusion Builder, the virtual host uses a naming convention *server name-virtual host name*. The Server drop-down list in Project properties displays the virtual host name using this naming convention. For example, if you created a virtual host named "vh1" in your ColdFusion server (localhost), the naming convention that ColdFusion Builder uses to identify the virtual host is "localhost-vh1".
 - **c** Port: The port assigned to the virtual host in the web server.
 - **d** Type: Select HTTP or HTTPS from the drop-down list.
 - e Document Root: Browse to or enter the home directory of the virtual host.
 - For example, if your website www.example.com is mapped to the directory C:\abc on the Apache web server, enter C:\abc as the home directory.
- 2 (optional) To create a virtual directory, click Virtual Directory, and enter the following details.
 - a Alias: Specify an alias for the folder path.
 - **b** Location: Browse to or enter the folder path to which you want to specify an alias.
 - For example, if the document root of your website (www.example.com) is c:\abc, and you want to include images from a folder available on d:\xyz\images. Then, you can define an alias called "images" for the folder path "d:\xyz\images". To understand more about virtual directories, see "Virtual directory" on page 47.
 - c Click Add.
 - **d** Click OK to add the virtual directory to the Virtual Directory Settings table.
- 3 Click Apply. The virtual host is added to the List Virtual Hosts table.

To modify the virtual host settings, select the virtual host from the List Virtual Hosts table, modify the settings, and click Update.

To understand more about virtual hosts, and its relevance in the ColdFusion Builder context, see "Virtual host" on page 47.

Install Extensions

Select Install Extensions to install the extensions that are packaged with ColdFusion Builder.

- 1 Browse and select the ColdFusion web root location.
- **2** Browse to a location within the web root to install the extension. The extension is installed in the Extensions directory within the selected location.

Click Finish to create the ColdFusion local server instance. For information on using these extensions, see "Using Extensions" on page 90.

Add a remote server

Before you add a remote server in ColdFusion Builder, do the following tasks.

Run the Admin server instance in the remote ColdFusion server

Depending on your remote server version and configuration, do the necessary tasks.

Standalone remote server version 7.0.2, 8.0.1

1 Unzip the file AdminServerComponents.zip to {CFHome}

The following files are copied to {cfhome}/runtime/bin:

- · adminstart.bat
- · admin_jvm.config
- · adminstart.sh

The Admin Server instance is copied to {cfhome}/runtime/servers

2 Go to {cfhome}/runtime/bin and run adminstart.bat (for Windows) or adminstart.sh (for Mac OS)

Multi-server/J2EE remote server version 7.0.2, 8.0.1

- 1 In the AdminServerComponents.zip file, unzip the following files to JRun_Home/bin:
 - · admin_jvm.config
 - adminstart.bat (for Windows) or adminstart.sh (for Mac OS)
- 2 Go to JRun_Home/bin and run adminstart.bat (for Windows) or adminstart.sh (for Mac OS)

Standalone/multi-server/J2EE remote server version 9

For version 9 of the remote server, the Admin Server components are shipped, by default.

- For standalone server configuration, go to {cfhome}/runtime/bin and run the adminstart script file.
- For multi-server or J2EE server configurations, go to JRun_Home/bin and run the adminstart script file.

Update security properties for the remote ColdFusion server

- 1 Go to {CFHome}/runtime/lib/security.properties
- 2 Update the values of jrun.subnet.restriction and jrun.trusted.hosts with the IP address of computer where ColdFusion Builder is installed. Alternatively, you can use the asterisk wildcard (*) as the IP address value, to allow the server to start and stop without any restriction.

Specify the remote server settings in ColdFusion Builder

In the Servers view, do one of the following:

- · Right-click and select Add Server.
- Click 🖺.

Enter the following details in the ColdFusion Server Setup wizard:

General Settings

- Server Name: ColdFusion server name.
- Description: (optional) Description of the server.
- Application Server: Select the drop-down list and select JRun or select Other to configure a non-Jrun server.

Note: You cannot start, stop, or restart a non-JRun server within ColdFusion Builder.

- · Host Name: Name of the remote server host.
- · Select Is Remote.

Note: When you enter a Host Name other than localhost or 127.0.0.1, Is Remote is automatically selected.

Other Settings

- Webserver Port: Specify the port number of the ColdFusion server instance you are configuring. The default port number of the ColdFusion server is 8500.
- Context root: (applicable only for JRun servers with J2EE configuration) Enter the context root.
 The J2EE environment supports multiple, isolated web applications running in a server instance. Hence, J2EE web applications running in a server are each rooted at a unique base URL, called a context root (or context path).
- Application Server Name: (applicable only for JRun servers with J2EE configuration) Name of the JRun Server on which ColdFusion is deployed.
- RDS User Name: (optional) If you are using RDS, specify the RDS user name.
- RDS Password: (optional) Specify the RDS password.

Note: You set the RDS password in the ColdFusion Administrator. Do not confuse the RDS password with the ColdFusion Administrator password, which is also managed through the ColdFusion Administrator.

- Select Enable SSL to enable SSL support in ColdFusion Builder. Servers registered in the Server Manager can communicate using SSL.
- Select Auto Start to automatically start the ColdFusion server every time you launch ColdFusion Builder.

Note: Auto Stop is not available for remote servers.

Click Next.

Remote Server Settings

- 1 Naming Port: Specify the naming port of the administrator server instance running on the remote server. By default, the naming port value is 2910. The naming port value is specified in {servers}/admin/SERVER-INF/jndi.properties. The port value of property java.naming.provider.url is the naming port/jndiport.
- 2 User Name: Specify the jmc user name, which is listed in the jrun-users.xml file.
- **3** Password: Specify the jmc password.
- **4** Document Root: Browse and select the web root location. If ColdFusion is configured with a web server, say IIS, then select the document root of the web server; for example, c:\inetpub\www.root.
- **5** Select the Mappings tab, and enter the following details. The mapping details are used for previewing and debugging files on the remote server.
 - Local path: Path that ColdFusion Builder uses to find projects or folders on the remote ColdFusion server.
 - Remote path: (optional if you specify the URL prefix) Path to the project on the remote ColdFusion server.

• URL prefix: (optional if you specify the remote path) Enter the URL prefix. To understand more about a URL prefix, and in what scenarios you can use a URL prefix, see "URL prefix" on page 46.

Note: You don't necessarily have to specify a URL when creating a server. You can specify a URL prefix even after creating the server by editing the server settings in the Servers view. You can also specify a URL prefix to an existing project or folder; for more information, see "Set URL Prefix" on page 58.

- · Click Add to add this mapping.
- 6 (optional) To configure a virtual host, select the Virtual Host Settings tab, and do as follows:

Note: When you specify a virtual host or virtual directory in ColdFusion Builder, corresponding settings must be specified in the configured web server. ColdFusion Builder does not validate these settings. So, if the settings in the web server are different from what you specify in ColdFusion Builder, ColdFusion Builder does not give an error.

- Click New and enter the following details in Virtual Host Settings section.
 - 1 Name: Specify a name for the virtual host. For example, vh1.

 Note: You can provide any name and not necessarily the name that you provide in the web server.
 - 2 Host Name: The virtual host name as specified in your IIS or Apache web server settings. For example, www.example1.com

When you create a virtual host in ColdFusion Builder, the virtual host uses a naming convention *server name-virtual host name*. The Server drop-down list in Project properties displays the virtual host name using this naming convention. For example, if you create a virtual host named "vh1" in your ColdFusion server (localhost), the naming convention that ColdFusion Builder uses to identify the virtual host is "localhost-vh1".

- **3** Port: The port assigned to the virtual host in the web server.
- 4 Type: Select HTTP or HTTPS from the drop-down list.
- 5 Document Root: Browse to or enter the home directory of the virtual host.

For example, if your website www.example.com is mapped to the directory C:\abc on the Apache web server, enter C:\abc as the home directory.

- (optional) To create a virtual directory, click Virtual Directory, and enter the following details.
 - 1 Alias: Specify an alias for the folder path.
 - 2 Location: Browse to or enter the folder path to which you want to specify an alias.

For example, if the document root of your website (www.example.com) is c:\abc, and you want to include images from a folder available on d:\xyz\images. Then, you can define an alias called "images" for the folder path "d:\xyz\images". To understand more about virtual directories, see "Virtual directory" on page 47.

- 3 Click Add.
- 4 Click OK to add the virtual directory to the Virtual Directory Settings table.
- Click Apply. The virtual host is added to the List Virtual Hosts table.

To modify the virtual host settings, select the virtual host from the List Virtual Hosts table, modify the settings, and click Update.

To understand more about virtual hosts, and its relevance in the ColdFusion Builder context, see "Virtual host" on page 47.

Click Next.

Install Extensions

Select Install Extensions to install the extensions that are packaged with ColdFusion Builder.

- 1 Browse and select the ColdFusion web root location.
- **2** Browse and select the ColdFusion web root location on the remote ColdFusion server.
- **3** Browse to a location within the web root to install the extensions. The extensions are installed in the Extensions directory within the selected location.

Click Finish to add the remote ColdFusion server instance. For information on using these extensions, see "Using Extensions" on page 90.

If the remote server is connected successfully, then the server status in ColdFusion Builder is displayed as Running. If the remote server is not connected successfully, the server status is displayed as Unknown. For more details about the error, see "Console view" on page 28.

Using Servers View

Use the Servers View to start, stop, and restart servers in ColdFusion Builder. You can also launch the ColdFusion Server Monitor and ColdFusion Server Administrator from the Servers View.

If the Servers View is not already displayed in the workbench, add the Servers View by selecting Window > Show View > Other. Then, in the Show View dialog box, select ColdFusion > Servers View.

Start, stop, restart, or delete a server

- 1 Right-click the server in Server View.
- **2** Select one of the following: Start Server, Stop Server, Restart Server, or Delete Server. Restart Server first stops and then starts the server.

Start ColdFusion Server Monitor

- 1 Right-click in the Server View.
- ${\bf 2} \quad {\bf Select\ Launch\ Server\ Monitor\ to\ open\ ColdFusion\ Administrator}.$
- **3** Specify the password.
- 4 Click OK to view the Server Monitor.

Start ColdFusion Server Administrator

- 1 Right-click in the Server View.
- 2 Select Launch ColdFusion Administrator.
- **3** Specify the username and password.
- 4 Click OK to view ColdFusion Administrator.

Import RDS server settings

If you have an RDS server configured, you can import the RDS server settings directly and add your RDS server to the Servers view.

- 1 Right-click in the Servers view, and select Add Server.
- 2 Select Import Configuration From RDS Server, and select the RDS server that you want to add to the Server view from the drop-down list.
- 3 Click OK.
- 4 To modify the RDS settings, specify changes in the Modify ColdFusion Server Setup dialog box, and click Finish.

You can now associate the server with your project, and debug, preview, and test your project.

Chapter 6: Managing Projects

About projects

Projects contains resources such as ColdFusion components, interfaces, and HTML and CFML pages that are used to develop ColdFusion applications.

Each project is stored in a default workspace. The workspace stores your projects and other metadata. The preferred workspace location is the ColdFusion document root

You can associate a project with a ColdFusion server. By doing so, you can test the project before final deployment.

Note: To preview files in your project using a web browser, ensure that you have set your project location to the ColdFusion document root.

To do any CFML development in ColdFusion Builder, you first create a ColdFusion project. To know more about creating a project in ColdFusion Builder, see "Creating a ColdFusion project" on page 55.

Creating a ColdFusion project

The Project Builder wizard guides you through the steps of creating a ColdFusion project.

Enter project information

- 1 Right-click in the Navigator area and click New > ColdFusion Project.
- 2 In the Project Builder wizard, specify the project name.
- 3 To change the default project location, deselect Use Default Location.
- 4 Click Next to specify the ColdFusion server details.

Enter server details

1 Select a server from the Server pop-up menu. If you have not configured a ColdFusion server, then click Add Server to add a server. For more information about setting up a ColdFusion Server, see "Adding ColdFusion servers" on page 47.

Note: If the project is in the server web root, then the Sample URL box is automatically populated with the server URL. For example, http://127.0.0.1:8500/eval, where 127.0.0.1 is the server host, 8500 is the port number, and eval is the project name.

- **2** Specify your preview settings to use an external web browser by selecting a web browser installed on your computer. The internal browsers are selected, by default.
- 3 Click Next.

Add existing sources

- 1 In this step, you can:
 - Link existing resources folder to the project.

- · Select previously configured applications, such as Model Glue, with the current project.
- **2** Click Add to select the folder to link to the project.
- 3 Click Finish to build a new ColdFusion project.

For more information about linking resources, see "Link to resources outside the workspace" on page 60.

Configure properties for projects and servers

You can use the Properties dialog box in ColdFusion Builder to configure project properties and server settings.

To open this dialog box, right-click the project in the Navigator view and select Properties.

Configure project properties

Select ColdFusion Project from the left pane of the Properties dialog box. You can add and remove external projects as links here.

Configure variable mappings

You use variable mappings to provide Code Assist for component variables that are not defined in the file being edited or in the included files.

- 1 In the Properties dialog box, you see a tree-view structure on the left. Select ColdFusion Variable Mappings.
- 2 Click New.
- 3 In the Variable Name field, specify the name of the variable to map, for example, application.cfc1
- 4 In the Mapped To field, enter the fully qualified name of the project variable, for example, com.adobe.mycfcs.cfc1

Configure server settings

- To open the ColdFusion Server Settings page, select ColdFusion Server Settings in the left pane of the Properties dialog box.
- To create a ColdFusion Server instance, use the Servers pop-up menu.

If you have already configured a server instance, you can assign it to your ColdFusion project. For more information about creating a server instance, see "Adding ColdFusion servers" on page 47.

Add ColdFusion pages, interfaces, and components

ColdFusion Builder provides wizards that guide you through the creation of ColdFusion pages, interfaces, and components.

Create a ColdFusion page

- 1 Right-click the ColdFusion project in the Navigator.
- 2 Click New > ColdFusion Page.
- 3 In the New ColdFusion Page wizard, specify a name for the ColdFusion (CFM) page.

4 Click Finish.

Create a ColdFusion component

- 1 Right-click the ColdFusion project in the Navigator.
- **2** Click New > ColdFusion Component.
- 3 In the New ColdFusion Component wizard, specify the following:
 - · Component name
 - Hint to identify the component (optional).
 - Any component that you want to extend.
 - Any interface that you want to implement.
- 4 Select the output type to be true or false.
- 5 Click Next.
- **6** Click Add to specify the component property details, such as the property name, display name, hint, and default value.
- 7 Enter or select a property type from the Type drop-down list.
- 8 (optional) Select Add Getter and select its access type from the Access drop-down list.
- 9 (optional) Select Add Setter and select its access type from the Access drop-down list.
- 10 Click OK to return to the New ColdFusion Component wizard.
- 11 To add functions to the ColdFusion component, click Add Function.
- 12 In the New Function wizard, specify the functions details, such as the function name, display name, hint, access type, return type, roles, and output type.
- 13 Click OK.
- 14 To add arguments to the selected function, click Add Argument.
- 15 In the New Function Argument dialog box, specify the argument name, display name, hint, argument type, and the default value of the argument.

Note: The options for the argument type are the same as the argument type options for ColdFusion Interface.

- 16 Click OK.
- 17 Click Finish to create a ColdFusion component (CFC file).

Note: You can use Outline View to navigate through the functions and tags that you add to your ColdFusion page or ColdFusion component.

Create a ColdFusion interface

- 1 Right-click the ColdFusion project in the Navigator.
- 2 Click New > ColdFusion Interface.
- 3 In the New ColdFusion Interface wizard, specify the interface name, hint, and display name.
- 4 To extend another interface, browse or specify the name of the CFC.
- 5 Click Add Functions to add a function and specify its details, such as the function name, function hint, return type, roles, and output (true or false).

- **6** Click Add Arguments to specify the arguments for the selected function. Enter or select an argument type from the Type drop-down list.
- 7 Click Finish to create a ColdFusion interface.

Add other files

You can also add the following types of files to your ColdFusion project:

- .html
- .js
- .css
- · .lxr (lexer file)
- .col (colorization file)
- .sdoc (ScriptDoc file)
- · Untitled versions of the preceding files

In addition, you can create generic text files, folders, and projects. You add these files to a project much as you add ColdFusion pages or components. To add any of these files to a project, do the following:

- 1 Right-click the project.
- 2 Select New > Other.
- 3 Expand Project Files to specify a filename or expand Untitled Files to create an untitled file.
- 4 Select the file that you want to create.
 - If you are creating an untitled file, click Finish.
 - If you selected Project Files, click Next and specify the filename. Then click Finish.

Set URL Prefix

- 1 In the Navigator view, select the project or folder for which you want to specify a URL prefix.
- 2 Right-click the selected project or folder and select Set URL Prefix.
- **3** Enter the URL for the selected resource.

Import, export, and delete projects

Import projects

You can import both ColdFusion and non-ColdFusion projects into ColdFusion Builder.

- 1 Right-click in the Navigator view and select Import.
- 2 In the Import wizard, select ColdFusion > Import Existing Projects.
- **3** In the Import ColdFusion Project dialog box, browse and select the project location. A list of all projects is displayed.
- 4 Click Refresh to search and refresh the project list.

- 5 Select Show All Projects to display all non-ColdFusion and non-ColdFusion Builder projects in the same location.
- **6** Select Add ColdFusion Nature To Non-ColdFusion Projects to apply ColdFusion Builder functionality, such as preview, editing, and debugging, to non-ColdFusion Builder projects.
- 7 Select the appropriate projects and click Finish.

Note: Importing a project retains the project properties including the server details, launching settings, browser details, application details, and linked folders.

Export projects

You can export files and folders from a ColdFusion Builder or non-ColdFusion Builder project to a designated location. However, for ColdFusion Builder projects, ColdFusion Builder functionality like server settings, preferences, and such are not exported.

- 1 Right-click in the Navigator view and select Export.
- 2 In the Export wizard, select ColdFusion > Export.
- 3 In the Export Project dialog box, browse and select the location where you want to export the project.
- 4 Click Select All to export all files and folders within the project, or click Filter Types to specify the files that you want to export.
- **5** Click Finish to export your project to the designated location.

Delete projects

When you delete a project, you remove the project from the current workspace. You can also remove the project from your computer's file system at the same time.

- 1 Right-click in the Navigator view and select Delete.
- 2 To remove the project from the workspace and the file system, select Delete Project Contents On Disk. The project is then permanently removed from the file system; you cannot undo the command.

Cloak projects and files


In ColdFusion Builder, you can cloak or hide files, file types, and folders from all synchronization, upload, download operations. This feature is useful if you have a large directory of files that you want to exclude from your synchronization or uploads.

You can cloak a file or folder in two ways:

- Right-click the file or folder in the Navigator view and select Synchronize > Cloak this file type. To uncloak the file type, right-click the file or folder and select Synchronize > Uncloak this file type.
- Set up your preferences to cloak certain file types, using wildcards and regular expressions by performing the following actions:
 - 1 Right-click the file or folder in the Navigator view and select Synchronize > Advanced Cloaking Preferences.
 - 2 In the Preferences dialog box, click the (+) icon.
 - 3 In the Ignore File/Folder dialog box, specify the file or folder name.
 - 4 Click OK. The specified file or folder is displayed in the list of files on which cloaking has been applied.

Link to resources outside the workspace

You can link to resources outside the project and workspace. This feature is useful when you have to use resources that are available on shared locations. The linked resource or the folder that contains linked resources appear as follows:



Link to resources outside workspace

- 1 In the Navigator view of ColdFusion Builder, right-click the project to add the linked resources to.
- 2 Select the resource that you want to link. For example, if you want to link to a folder, select New > Folder.
- **3** Enter a name for the resource that you are linking. If you do not enter a name, the default name of the resource is taken.
- 4 Click Advanced.
- 5 Select Link to folder in the file system. Enter or browse to the resource location.
- **6** Click Finish to link the resource to your project.

Use path variables to link to resources

When you link to resources, you can define path variables instead of providing the full path to where the resource is stored. You can define a path variable and then set the path to the resource that you want to link to.

- 1 In the Navigator view of ColdFusion Builder, right-click the project to add the linked resources to.
- 2 Select the resource that you want to link. For example, if you want to link to a folder, select New > Folder.
- **3** Enter a name for the resource that you are linking. If you do not enter a name, the default name of the resource is taken.
- 4 Click Advanced.
- 5 Select Link to folder in the file system. Enter or browse to the resource location.
- 6 Click Variables.
- 7 You can select an existing path variable or click New to create a path variable.

Note: The list of existing resource variables is also available by selecting Window > Preferences from the main menu and then selecting General > Workspace > Linked Resources. You can edit and create linked resource variables using the Linked Resources dialog box.

- **8** To create a path variable, enter a name for the resource and browse to or provide the full path to the resource. Click OK to add the path variable to the path.
- **9** Click Finish to link the resource to your project.

Deploy projects over FTP and Secure FTP connections

ColdFusion Builder lets you deploy ColdFusion projects on a web server using File Transfer Protocol (FTP).

ColdFusion Builder also supports file transfers using Secure File Transfer Protocol (SFTP) and File Transfer Protocol Secure (FTPS) connections. SFTP and FTPS are a secure form of FTP, which encrypt the files that you send and receive to a remote server.

Create an FTP or secure FTP connection in ColdFusion Builder

- 1 Right-click the project in the Navigator view.
- 2 Click Synchronize > Create New Synchronize Connection.
- **3** Specify a name for the connection.
- 4 Select the ColdFusion project or file to deploy by selecting the Local drop-down list and the location that contains the file or project.
- 5 Select a remote server, and enter the following details in the New Connection Dialog Box.
 - **a** Site name: Name of the new remote site.
 - **b** Select the connection type.
 - **c** Server: URL of the site to connect to (for example, admin.myWebSite.com). You can also enter the IP address of the site.
 - **d** Username/Password: User name and password of the server.
 - **e** Use Public Key Authentication: This option is available only if you select SFTP as the connection type. Public key authentication lets you select a key-pair on your computer, and you copy the public key to the server.
 - **f** Remote path: If you want to connect to a subfolder under the root of the remote site, specify the folder path.
 - **g** Click Advanced Options to specify the following:
 - Port: If you want to use a port other than 22, specify the port.
 - If you want the FTP connect session to run in the background, select Use Passive Mode.
 - If you work in a team environment, you sometimes want to upload files that overwrite others' changes. If so, select Calculate Server/Client Time Offset Automatically as a precaution.
- 6 Click OK to add the FTP connection.

Upload, download, or synchronize projects, files, and folders

- 1 Right-click the project or file in the Navigator view and select Synchronize > Upload or Download.
- **2** From the Choose Site Connection dialog box, select the connection.
- 3 Click OK.

Import Ajax libraries

- 1 In the Navigator view, right-click the project in which you want to import Ajax libraries, and click Import.
- 2 In the Import wizard, select ColdFusion > Ajax Library Import Wizard, and click Next.
- 3 Select the Ajax libraries that you want to import, and click Finish.

Working with Flash Builder projects

To work with a Flash Builder project in ColdFusion Builder, import the Flash Builder project into ColdFusion Builder. After that, apply ColdFusion Builder functionality by selecting the Flash Builder project in the Navigator view, then right-click and select Apply ColdFusion Nature.

Applying ColdFusion Builder functionality to the Flash Builder project lets you preview, edit, and debug the Flash Builder project from within ColdFusion Builder.

Developing AIR applications

Adobe ColdFusion Builder provides you with tools to create Adobe® AIR® projects, debug, package, and digitally sign Adobe AIR applications.

Create an AIR project

- 1 Select File > New > Project.
- 2 In the Create Project wizard, select HTML Projects > Adobe AIR Project, and click Next.
- 3 Enter the project name and the location of the files in the project.
- 4 Specify the HTML start page that contains the sandbox application code. You can also select non-application sandbox code. Click Next.
- 5 Specify the following properties of the application XML file, and click Next.
 - ID: Unique application ID that is the identifier string for the application.
 - · Name: Application name
 - Filename: Name of the file and folder where the application is installed
 - Version: Application version
 - Icon: Icon files that represent the application. If you don't specify an icon, the operating system uses a default icon.
- 6 Specify the window style, dimension, sizing options, and click Next.
- 7 Select the AIR frameworks to import into the project, and click Next.
- 8 Select the Ajax JavaScript libraries that you want to import, and click Finish to create your AIR project.

Run and debug an AIR application

- 1 From the Navigator view, open the source file (Application.XML) for the application.
- **2** Click Run on the main toolbar to launch the AIR application.
- **3** To debug the application, click 🏇 in the workbench toolbar.

The application launches and runs in the ADL application (AIR Debugger Launcher). The ColdFusion debugger catches any breakpoints or runtime errors and you can debug the application like any other ColdFusion application. For more information, see "Debugging Applications" on page 64

Package and digitally sign an AIR application

When your application is complete and ready to be distributed, you package it into an AIR file. Packaging consists of the following steps:

- 1 From the Navigator view, right-click the AIR project that you want to package, and click Export.
- 2 In the Export wizard, select Adobe AIR > Adobe AIR Package, and click Next.
- **3** Select the AIR project and the application descriptor file.
- **4** You can select the default AIR SDK or configure a different Adobe AIR SDK, and click Next. To configure a different AIR SDK, click Configure Adobe AIR SDKs, and select an AIR SDK. You can also add a new AIR SDK, or edit and remove an existing AIR SDK.
- 5 You can digitally sign your AIR application by selecting an existing digital certificate or by creating a self-signed certificate. Digitally signing your AIR application provides assurance to the users that the application has been signed with a trusted certificate and displays the publisher identity.
 - a Select Digitally Sign Exported AIR Application.
 - **b** Select an existing digital certificate, or click Configure Certificates to select a different digital certificate. Click Add to create a self-signed certificate.
 - **c** Specify the password for your digital certificate.
 - **d** If you select TimeStamp AIR Package, when signing the installation package, the AIR Developer Tool (ADT) automatically contacts a time-stamp authority to verify the time. The time-stamp information is included in the AIR file. An AIR file that includes a verified time stamp can be installed at any point in the future.
 - e Select Migrate AIR Application to migrate an AIR application to a new certificate. When you do so, sign the AIR file with both new and old certificates. Select the previous certificate from which you want to migrate and the previous certificate password.

You also have the option of packaging your AIR application without a digital signature. To do so, deselect Digitally Sign Exported AIR Application. When you package your AIR application without a digital signature, an intermediate AIR file (.airi) is created. An intermediate AIR file cannot be deployed or installed. It is generally used for testing (by the developer) and can be launched using the AIR ADT command-line tool.

- 6 Click Next to optionally select files to exclude from the exported AIR file. By default, all the files are included.
- 7 Click Finish to generate the AIR file.

Chapter 7: Debugging Applications

Debugging lets you examine and troubleshoot your application. When you debug, you can control when the application must stop at specific points in the code. You can also monitor important variables and test your code. Debugging uses a configuration to control how applications are launched. When you debug your application, you run the debug version of the application file.

Using ColdFusion debugger

Before you use the ColdFusion Debugger, ensure that you do the following:

Set up ColdFusion to use the Debugger

Before you use the Debugger, ensure the following:

- A server is associated with the project or the project containing the files that you want to debug.
 - 1 In the Navigator view, right-click the project and select Properties.
 - 2 In the Properties dialog box, select ColdFusion Server Settings.
 - **3** Under Select Servers, ensure that a server is selected. If no server is selected, select the Servers drop-down list and select an available server, or select Add Server to configure a new server.
- RDS is enabled on the ColdFusion server, and you have specified the correct RDS configuration information in ColdFusion Builder.
- Debugging is enabled in ColdFusion Administrator.
 - 1 In ColdFusion Administrator, select Debugging & Logging > Debugger Settings.
 - **2** Select Allow Line Debugging.
 - **3** Specify the port to use for debugging. The default value is 5005.
 - 4 Specify the maximum number of simultaneous debug sessions. The default value is 5.
 - **5** Click Submit Changes.
 - **6** To increase the time after which requests time out, do the following:
 - a Select Server Settings > Settings.
 - b Select Timeout Requests After (Seconds) and enter the required timeout value. For example, 300.
 - c Click Submit Changes.
 - 7 The debugger server listens for commands from ColdFusion Builder on a separate port than the one specified in step 3. By default, ColdFusion launches the debugger server with a random available port. This could be a problem if ColdFusion (and hence debugger server) is behind a firewall. Because, the firewall blocks the random port that the debugger is listening.
 - To prevent this problem, specify a fixed debugger server port number and allow this port in the firewall. To set a fixed debugger server port number, specify the following JVM argument on the Java And JVM page of the ColdFusion Administrator (or the appropriate place for your J2EE Application Server). Replace portNumber with the port that you want to use:

- -DDEBUGGER SERVER PORT=portNumber
- **8** Restart ColdFusion. If you are running the J2EE configuration of ColdFusion, restart the server in debug mode with the debug port as specified.

Set up debugging for J2EE configuration of ColdFusion

1 If you are not running the server configuration of ColdFusion, specify Java debugging parameters in the configuration file or startup script of the application server you are running. The parameters must look like the following:

```
-Xdebug -Xrunjdwp:transport=dt_socket,server=y,suspend=n,address=<port_number>
```

Ensure that the port number you specify is the same port number specified on the Debugger Settings page of ColdFusion Administrator.

If you are running the server configuration, ColdFusion writes these debugging parameters to the jvm.config file when you use the Debugger Settings page of the ColdFusion Administrator.

- 2 If you are not running the server configuration and your application server is not running on JRE 1.6, copy the tools.jar file of the JDK version that your application server is running to the \lib folder of ColdFusion. For example, if you are running JRun that runs on JRE 1.4, copy the tools.jar file of JDK 1.4 to the \lib folder of ColdFusion.
- 3 If you are running the server version of ColdFusion and you specify a JRE version other than JRE 1.6 in the jvm.config file, copy the tools.jar file of the JDK version specified in your jvm.config file to the \lib folder of ColdFusion.

Set up debugging for multi-server configuration of ColdFusion

To debug ColdFusion applications running on the multiserver configuration, start the ColdFusion server from the command line using the following command:

```
jrun -config <path_to_jvm_config> -start <server_name>
```

Specify debugger settings in ColdFusion Builder

- 1 In ColdFusion Builder, select Window > Preferences.
- 2 In the tree view, select ColdFusion > Debug Settings.
- **3** Specify the home page URL that points to the page that appears in the Debug Output Buffer of the debugger when you click the Home button.
- 4 Specify the extensions of the types of files that you can debug and debugger scopes that you want the Debugger to recognize. To improve performance when debugging large files, deselect all scopes for which you do not require information.
- 5 Select Break On CFML Runtime Exception to stop the debugger on the line that causes a ColdFusion error.
- **6** Select Log An Exception To The Eclipse Error Log to display the server logs in the TailView view instead of showing a warning dialog.


Debugging your application

After you enabled the debugger in the ColdFusion Administrator and configured the debugger in ColdFusion Builder, you can debug projects in ColdFusion Builder.

Create or edit launch configurations

When you debug a project in your application, ColdFusion Builder creates a project-specific launch configuration for the first time that you debug. The launch configuration automatically defines a project name (based on the project that you are debugging), main application file, and the path to debug the application.

Launch configurations are managed through the Create, Manage, and Run Configurations dialog box.



Debug configuration

You can edit the default launch configuration that ColdFusion Builder creates.

- 1 Select the project to debug in the Navigator view.
- 2 You can access the launch configuration in the following ways:
 - Select Run > Debug or Run > Debug Configurations
 - Select 🏇 in the workbench toolbar.
 - Right-click the project and select Debug As > Debug Configurations.
- **3** Select the launch configuration to edit in the Debug Configurations dialog box. You can also create a launch configuration or base a new configuration on an existing configuration.
- 4 Click the Perspectives link to modify the launch configuration preferences, as required.

Run the application

Run the application that you want to debug before setting any breakpoints. Running the application before debugging compiles the application and improves performance during debugging.

- 1 Select the project to run in the Navigator view.
- 2 Select or modify the Run configuration using the Run Configurations dialog box. You can access this dialog box in the following ways:
 - Select Run > Run configurations.
 - Right-click the project and select Run As > Run Configurations.
- 3 Select the configuration to run or modify, if necessary.
- 4 Click Run.

The application is run in your computer's default browser. To specify a different external browser, do as follows:

- (Windows) Right-click the project and select Properties. Go to ColdFusion Server Settings, and select a a web browser installed on your computer.
- (Mac) In the Preferences dialog box, select General > Web Browser, and select a web browser installed on your computer.

Set and remove breakpoints

You use breakpoints to control the running of your application so you can inspect your code and debug your application. You add breakpoints in the code editor and then manage them in the Breakpoints view. You can also set breakpoints as you write code or while you debug.

For more information about managing breakpoints using the Breakpoints view, see "Breakpoints view" on page 26.

ColdFusion breakpoints

ColdFusion breakpoints have the following four states in the ColdFusion debugger:

Enabled and Valid This state indicates that the breakpoint is at a valid location. The breakpoint appears as a solid blue circle in the left margin of the CFML Editor. Code execution stops when this breakpoint is encountered.

Unresolved ColdFusion sets the breakpoint for the page that is loaded in its memory. If you modify the page and do not run it, the source is no longer in sync with the page on the server. In this situation, ColdFusion sometimes does not know whether the line where you want to set the breakpoint is valid. A question mark (?) represents this type of breakpoint.

Invalid If ColdFusion determines that the CFML that you are editing in ColdFusion Builder is the same as the CFML in its memory, and that the breakpoint you have set is at an invalid line, the breakpoint appears as a red X.

Disabled This state indicates that the breakpoint is disabled.

Set a breakpoint in the code editor

- 1 Open the ColdFusion Builder project that contains the code in which you want to set breakpoints.
- 2 Locate the line of code where you want to set a breakpoint, and do one of the following:
 - Double-click in the marker bar along the left-edge of the editor.
 - Select Run > Toggle Breakpoint or Run > Toggle Line Breakpoint.

Note: Toggle Method Breakpoint and Toggle Watchpoint are not supported in ColdFusion Builder.

3 You can set breakpoints in your CFML file to stop executing the page at particular points. When you set a breakpoint on a line, the CFML stops executing just before that line. For example, if you set a breakpoint on the third line in the following CFML page, execution stops before <cfset myName = "Wilson">.

```
<cfset yourName = "Tuckerman">
<cfoutput>Your name is #yourName#.</cfoutput>
<cfset myName = "Wilson"</pre>
```

A blue dot appears before the line on which you set the breakpoint.

You can also view a list of breakpoints set in the current project in the Breakpoints view of the ColdFusion Builder Debugging perspective.

Skip all breakpoints in the code editor

After setting breakpoints in your code, you can ignore all breakpoints at the time of debugging.

- 1 Open the ColdFusion Builder project that contains the code with breakpoints.
- 2 In the Breakpoints view toolbar, select Skip All Breakpoints.

Remove a breakpoint in the code editor

In the marker bar along the left-edge of the editor, double-click an existing breakpoint.

The breakpoint is removed from the marker bar and the Breakpoints view of the ColdFusion Builder Debugging perspective.

To remove all the breakpoints in the file, select Run > Remove all Breakpoints from the main toolbar menu.

Start a debugging session

- 1 In the Navigator view, select the project or file to debug.
- 2 You can start the debugging session in the following ways:
 - Select Run > Debug
 - Click 🏇 in the workbench toolbar.
 - Right-click the project and select Debug As > ColdFusion Application.

The Debug launch configuration is automatically created and launched.

Note: If you are debugging a page and then try to browse to or refresh that page, it can result in unexpected behavior in the Debugger.

Manage the debugging session

Use the Debug view to control the debugging of the application, to suspend, resume, or terminate the application, or to step into or over code.

For information about the various views in the ColdFusion Debug perspective, see "ColdFusion Debugging perspective" on page 24.

Run code line by line

You can use the Step Into, Step Over, and Step Return buttons to proceed through your CFML application line by line.

For the stepping process to work properly, clear the cache of compiled classes. To do so, recompile all CFML pages compiled with an earlier version of ColdFusion.

In large files, you sometimes find that stepping and breakpoints are slow. To improve performance, do the following:

- 1 In ColdFusion Builder, select Windows > Preferences.
- 2 In the tree view, select ColdFusion > Debug Settings
- **3** Deselect all scopes for which you do not require information.

Step Into

Use Step Into for UDFs, CFCs, custom tags, and included files.

Avoid using Step Into on CFML tags such as the cfset tag. Step Into is more performance intensive than Step Over.

When stepping into functions, tags, and files, the file must be displayed in one of the open projects. The file that you are stepping in must be in an open project.

Step Over

Use Step Over to proceed through your CFML application, bypassing included files, such as UDFs or CFCs.

Step Return

Use Step Return to return to the original page from which you entered the included file, such as UDFs or CFCs.

Inspect variables

As you run CFML code, you can see the values and scope of variables in the Variables view. Only variables whose scopes are what you selected in the Preferences dialog box appear in the Variables view. For more information about using the Variables view, see "Variables view" on page 25.

Watch expressions

Watch expressions are useful to watch critical variables that sometimes go out of scope when you step into a different function. You can create your own expressions to watch and evaluate. You can modify the expressions during the debugging session.

You can do the following in the Expressions view:

- Create a watch expression by right-clicking and selecting Add Watch Expression. You can then enter the expression
 in the Add Watch Expression dialog box.
- · Ignore a watch expression that you've added by right-clicking the expression and selecting Disable.
- Edit a watch expression by right-clicking the expression and selecting Edit Watch Expression. You can then modify the expression.

For more information about using the Expressions view, see "Expressions view" on page 26.

Debugging remote applications

If ColdFusion is running on a remote server, configure a remote server connection and specify a mapping between ColdFusion and ColdFusion Builder. Mapping ensures that ColdFusion Builder and ColdFusion are working on a copy of the same project or file.

1 To configure a remote server, see "Add a remote server" on page 50. Enter the RDS configuration information, as required.

- 2 In the Server view, right-click the server and select Edit Server. In the Mappings screen of the Server wizard, enter the following mapping details:
 - Local Path: Path that ColdFusion Builder uses to find projects or folders on the remote ColdFusion server.
 - Remote Path: Path to the project or folder on the remote ColdFusion server.

Note: You can specify multiple mappings between the remote ColdFusion server and ColdFusion Builder.

For example, if you are editing files in a ColdFusion project that points to D:\MyCoolApp and the corresponding files exist on a remote server at D:\Shared\websites\MyCoolSite. Then, create a mapping by specifying the local path as D:\MyCool App and the remote path as D:\Shared\websites\MyCoolSite.

When you deploy the files to the ColdFusion server, you copy them to W:\websites\MyCoolSite\, which the ColdFusion server recognizes as D:\Shared\websites\MyCoolSite.

The mapping in ColdFusion Builder specifies that the ColdFusion Builder directory is D:\MyCoolApp and the server is D:\Shared\websites\MyCoolSite. So, ColdFusion Builder translates the file path (D:\MyCoolApp\index.cfm) to a path that the ColdFusion server recognizes (D:\Shared\websites\MyCoolSite\index.cfm).

To see more information about the interaction between the client and the server, add the following to the JVM arguments in the ColdFusion Administrator:

```
-DDEBUGGER_TRACE=true
```

3 In the Navigator view, select the project or file to debug and click 🐉 in the workbench toolbar.

Chapter 8: ColdFusion Builder Extensions

About extensions

You can extend the ColdFusion Builder IDE (Integrated Development Environment) functionality to support various ColdFusion frameworks and code generation requirements. You develop ColdFusion Builder extensions to generate code, design dynamic user interfaces, and perform basic CRUD (Create, Read, Update, and Delete) operations on the database. The ColdFusion Builder extension is a structured component that adds context menus in the ColdFusion Builder IDE and handles events on these menus. You, the ColdFusion developer, can develop a ColdFusion Builder extension yourself or you can install an available extension.

To develop your own ColdFusion Builder extension, you create the configuration file and handler files. You define the context menus and events in the configuration file - IDE_Config.xml. For more information, see "Developing extensions" on page 71.

ColdFusion Builder lets you extend the IDE at various levels including creating user interfaces. For more information, see "Creating user interfaces for extensions" on page 82.

The extensions that are shipped along with ColdFusion Builder are Adobe CFC Generator, Model-Glue Assistant, and AS Class Generator. You can install and integrate these extensions with ColdFusion Builder. For more information, see "Using Extensions" on page 90.

ColdFusion Builder provides the ColdFusion Builder Extension Creator to guide you through the process of creating and packaging extensions. For more information, see "Use ColdFusion Builder Extension Creator to create and package extensions" on page 88.

Developing extensions

To develop a ColdFusion Builder extension, you create the following elements:

- Configuration file (IDE_config.xml)
- Handler files (CFM files)

You can create these elements by writing the code or by using the ColdFusion Builder Extension Creator wizard. For more information about using the ColdFusion Builder Extension Creator wizard, see "Use ColdFusion Builder Extension Creator to create and package extensions" on page 88.

Configuration file

Creating the configuration file (IDE_config.xml) is an important step in developing a ColdFusion Builder extension. You define all the elements of the configuration file within the application tag.

Specifying metadata elements

You use metadata elements to create an extension and specify information like, extension name, author, version, and extension description.

Use the following elements to specify application metadata in the configuration file.

Element	Description	
name	The name of the extension.	
author	The author's name.	
version	The file version.	
email	Specifies the e-mail address.	
description	A brief description of the application.	
	The description can be in plain text or you specify a path to an HTML file, which contains the application description. If you specify a path to an HTML file, store the HTML file in the Install directory within the extension.	
license	License agreement displayed when installing the extension.	
	The license agreement can be displayed in plain text or you specify a path to an HTML file, which contains the license agreement. If you specify a path to an HTML file, store the HTML file in the Install directory within the extension.	

Adding pages to the ColdFusion Builder Extension Installation wizard

When you define the Configuration file, you can specify code that adds screens to the ColdFusion Builder Extension Install wizard. You can use these screens to get user inputs. Generally, user inputs are required for performing any configuration tasks after installation.

You specify input details using the input tag; for information on how to specify input tags, see "Specifying input types" on page 76. The handler that is specified in the handlerid attribute of the wizardtag is called with the input details. You can also specify the height and width of the Install wizard using the height and width attributes of the wizard tag. You can specify the title for each page in the wizard using the title attribute of the page tag.

Syntax

```
<application>
<name>Name of the ColdFusion Builder extension</name>
<install>
<wizard height="" width="" handlerid="handlerID" >
<page title="Wizard page title" >
<input name="Input" ... />
<input name="Input" ... />
</page>
</wizard>
</install>
</application>
```

In the following example, once the Extension Installation wizard finishes installing the extension, the handler ID, postinstallhandler, is called with the specified input details.

```
<application>
<name>ORM CFC Generator</name>
<install>
<wizard height="" width="" handlerid="postinstallhandler" >
<page title="Install settings" >
<input name="Mapping" ... />
<input name="Datasource" ... />
</page>
</wizard>
</install>
</application>
```

Extending IDE

You can extend the ColdFusion Builder IDE at the following levels:

- Adding context menus: You can add context menus to the following views:
 - · Resource navigator
 - · RDS Data view
 - · Outline view
 - · CFML Editor
- Handling workspace events: Currently onprojectcreate is the only supported event.

You can specify handlers for the context menus and events to perform CRUD or code generation operations.

Specifying Handlers

ColdFusion Builder supports CFM handlers. In the ColdFusion Builder context, a handler is a file that contains code, which is run in response to an event or an action. You specify handlers within the handlers tag. Use the handlerid attribute to associate the handler with an event or action. Specify all handler details within the handlers tag. For more details on specifying events and actions, see "Specifying events" on page 74 and "Specifying context-menus" on page 74. All the handler files must be stored in the Handlers folder.

Syntax

Attribute	Description
id	Handler ID
type	Specifies the handler type.
	The handler type you can specify is "CFM"
filename	The name of the CFM file

Note: You can specify only alphanumeric characters for the attribute values. Special characters are not allowed.

Specifying events

Use the events tag to specify events. Currently, ColdFusion Builder only supports an event on project creation. The supported event type is onprojectcreate. Pass the required handler ID for the onprojectcreate event. When the event occurs, the handler associated with the handler ID is called.

All applications for which the onprojectcreate event is specified are listed under the list of applications in the "Creating a ColdFusion project" on page 55. When a user selects any of the listed applications, the associated handlers for the selected application are called. The onprojectcreate event is useful in creating a basic project structure for a given ColdFusion Builder extension.

Syntax

Attribute	Description
type	Specifies the event for which the handler runs.
	You can specify the event type="onprojectcreate"
handlerid	Specifies the handler ID to pass.

Note: You can specify only alphanumeric characters for the attribute values. Special characters are not allowed.

Example

```
<events>
     <event type="onprojectcreate"
     handlerid="projectCreationHandler" />
     </events>
```

Specifying context-menus

Use the menucontributions tag to specify a context-menu. A context-menu is a pop-up menu that appears on a right-click event.

To specify menu contributions for different views, use the contribution tag. Use the target attribute within the contribution tag to specify the target view where the menu must appear. Use the menu tag within the contribution tag to specify the menu to add. Use the action tag within the menu tag to specify menu items.

Syntax

contribution

Attribute	Description	
target	The target view can be any of the following:	
	• rdsview	
	projectview	
	outlineview	
	• editor	

Note: You can specify only alphanumeric characters for the attribute values. Special characters are not allowed.

menu

Attribute	Description
name	Specifies the name of the menu.

Note: You can specify only alphanumeric characters for the attribute values. Special characters are not allowed.

action

Attribute	Description
name	Specifies the name of the action.
handlerid	Specifies the ID of the associated handler.
showresponse	A Boolean that value that specifies if the HTML response that the handler receives must be shown to the user:
	• yes
	• no
	The default value is false.

Note: You can specify only alphanumeric characters for the attribute values. Special characters are not allowed.

Specifying menu filters

Menu filters help control where a menu or menu item must appear. You specify menu filters using the filters tag. You can specify different filter types within the filters tag; use the type and pattern attributes to specify where the menu or menu item must appear. If any of the specified filters match, the specified menu or menu item appears.

You can specify filters for both menus and actions. If you specify the filter tag within the menu tag, the filter controls the display of the menu. For example, in the following code, the ORM Code Generator menu appears only if the user right-clicks the modelglue.xml file.

```
<menu name="ORM Code Generator">
<filters>
<filter type="file" pattern="modelGlue.xml" />
<filters>
</menu>
```

Specifying filters for the Navigator View

You can specify filters on the project, folder, or file of the Navigator view.

Syntax

```
<filter type="folder|project|file"
pattern="regular expression to match folder, project, or filename" />
```

Example

If you want the ORM Code Generator menu to appear only in the context of a folder, you can use code like the following:

```
<menu name="ORM Code Generator">
<filters>
<filter type="folder" />
<filters>
</menu>
```

Specifying filters for the Outline View

You can specify filters on different node types of the Outline view. The node name that you specify acts as the filter. In the Outline view, you can also specify filters for files. When you open the file that matches the filter in the CFML editor, the contributed menu appears in the Outline view.

Syntax

```
<menu name="menu name">
<filters>
<filter type="node name" />
```

Example

If you want the ORM Code Generator menu to appear only on the CFfunction node in the Outline view, you can use code like the following:

```
<menu name="ORM Code Generator">
<filters>
<filter type="cffunction" />
```

Specifying input types

Before a handler is called, you can get user inputs using the input tag. The associated handler processes the user inputs. You specify an input tag for every action and the input tag must be within the action tag.

To control the height and width of the input dialogs, you specify the input tag within the dialog tag. For example, you can specify code like the following:

```
<dialog height="400" width="600" title="title" image="path to the image file">
<input name="Mapping" ... />
<input name="Datasource" ... />
</dialog>
```

Attribute	Description	
height	Specifies the height of the dialog.	
width	Specifies the width of the dialog.	
title	Specifies the title for the dialog.	
image	Specifies the path to the image that appears in the title bar. The path that you specify must be relative to the Extension folder.	

Syntax

Attribute	Description	
name	Input variable name	
label	The label of the input dialog box	
tooltip	The tool tip that appears when the user moves the mouse over the input dialog box.	
type	The input variable can be any of the following data types: • dir • string • Boolean • file • password • list • projectdir • projectfile	
required	Specifies the input field as required. When you specify an input field as required, the OK button is not enabled until the user enters a value in the required field.	
pattern	Specifies the regular expression against which user input is validated. For a validation error, you can specify the error message that must appear. You use the errormessage attribute to specify the error message.	
errormessage	The error message that appears when validation fails for a given pattern.	

Attribute	Description	
helpmessage	The Help tip that appears in the title area of the dialog for a given input field.	
default	Specifies a default value for a given input type. You cannot specify a default value for Boolean input types. For lists, the default value is preselected.	
checked	A Boolean value that specifies if the check box field is selected or deselected, by default:	
	true - check box is selected (default value).	
	false - check box is deselected	

Note: You can specify only alphanumeric characters for the attribute values. Special characters are not allowed.

Each data type corresponds to an input type as specified in the table below. The syntax for each input type is also specified.

Datatype	Input type	Syntax
dir	Directory selection field	<pre><input label="label" name="input variable name" tooltip=" tooltip" type="dir"/></pre>
string	Text field	<input <br="" name="input variable name"/> label="label" tooltip=" tooltip" type="string"/>
boolean	Check box	<input label="label" name="input variable name" tooltip=" tooltip" type="boolean"/>
file	File selection field	<pre><input label="label" name="input variable name" tooltip=" tooltip" type="file"/></pre>
password	Password field	<pre><input label="label" name="input variable name" tooltip=" tooltip" type="password"/></pre>
list	List field	<pre><input label="label" name="input variable name" tooltip=" tooltip" type="list"/> <option value="Option1"> <option value="Option2"> </option></option></pre>
projectdir	Project directory selection field	<input label="label" name="input variable name" tooltip=" tooltip" type="projectdir"/>
projectfile	Project file selection field	<pre><input label="label" name="input variable name" tooltip=" tooltip" type="projectfile"/></pre>

```
<menucontributions >
    <contribution target="rdsview" >
        <menu name="ORM Code Generator">
            <action name="Generate ORM CFC" handlerid="cfm1" >
                <input name="Location" label="Enter location"</pre>
    tooltip="Location where generated CFCs will be stored" type="dir"/>  
                <input name="generateAppCFC" label="Generate</pre>
   Application CFC" tooltip="Generate Application CFC along with ORM CFC"
    type="boolean"/>
                <input name="generateView" label="Generate View"</pre>
                tooltip="Generate View template along with ORM CFC" type="boolean"/>
            </action>
            <action name="Generate Ajax Grid" handlerid="cfm2" >
                <input name="Location" label="Enter location"</pre>
                tooltip="Location where generated View will be stored" type="dir"/>
            </action>
        </menu>
    </contribution>
    <contribution target="projectview" >
        <menu name="ORM Code Generator">
            <action name="Generate ORM CFC" handlerid="cfm1" />
            <action name="Generate Ajax Grid" handlerid="cfm2" />
        </menu>
    </contribution>
    <contribution target="outlineview" >
        <menu name="ORM Code Generator">
            <action name="Generate ORM CFC" handlerid="cfm1" />
            <action name="Generate Ajax Grid" handlerid="cfm2" />
        </menu>
    </contribution>
</menucontributions>
```

Keyword support

ColdFusion Builder supports keywords that are used to add default values in input dialogs. During runtime, actual values replace the keywords.

The following table lists the supported keywords and the corresponding actual values.

Keyword	Actual value
projectlocation	Absolute path to the project location
projectname	Name of the project
serverhome	Absolute path to the serve installation location
wwwroot	Server web root

For example, you can specify the projectname keyword as follows:

```
<input name="projectname" label="projectname" default="{$projectname}" type="dir"/>
```

For information about importing, reloading, packaging, and debugging extensions, see "Using the Extensions view" on page 87.

Understanding ColdFusion Builder and handler communication

Communication between the handler and ColdFusion Builder IDE is through XML. When an event occurs, ColdFusion Builder sends the event details to the associated handler in XML format. The XML is sent to the handler as a FORM-scope variable named ideEventInfo. To retrieve the XML from the FORM-scope variable, use the cfparam tag in the handler.

Syntax

```
<cfparam name="ideeventinfo">
or
<cfset ideData= form.ideEventInfo >
```

Understanding XML structure

To understand the XML structure, let us review the XML code.

Consider the following points before reviewing the code:

- All information sent to the handler is within the event tag.
- · All event and action information is within the ide tag.
- Any user inputs are within the user tag.

The following table describes the XML code. The contents of the XML code vary depending on the event.

Code	Context	Description
<pre><rdsview></rdsview></pre>	rdsview	When you click a menu item of the RDS view, the event details are sent to the associated handler.
<pre><pre><pre><pre><pre><pre><pre><pre></pre></pre></pre></pre></pre></pre></pre></pre>	projectview	When you click a menu item of the Project view, the event details are sent to the associated handler.
<pre><outlineview projectlocation="" projectname=""> <source filename="" path=""/> <node type="function/other"> <function name="" returntype=""> <argument name="" type=""></argument> </function> </node> </outlineview></pre>	outlineview	When you click a menu item of the Outline view, the event details are sent to the associated handler.
<pre><eventinfo eventtype="" projectlocation="" projectname=""> <resource name="" path="" type="file/folder/project"></resource> </eventinfo></pre>	on project create	When the specified event occurs, the event details are sent to the associated handler.
<pre><user> <input name="" value=""/> <input name="" value=""/> <input name="" value=""/> </user></pre>	input dialog	All user inputs are specified within the user tag. Each input tag within the user tag, contains specific user input. The input name is the same as the input name specified in the IDE_Config.xml file.
<user> <page index=""> <input name="" value=""/> </page> </user>	Install wizard	All user inputs are specified within the user tag and sent to the handler associated with the Install wizard. Each input tag within the user tag contains specific user input. The input name is the same as the input name specified in the IDE_Config.xml file.

Creating user interfaces for extensions

Create input dialogs

You can create an input dialog either by using a configuration file (IDE_Config.xml) or using CFM pages.

Note: If you are creating a user interface using XML response, turn off the debug output by specifying cfsetting showdebugoutput="no" in the relevant code.

Using the configuration file

You create an input dialog by creating a configuration file (IDE_config.xml) and specifying the necessary details. For more information, see "Configuration file" on page 71.

For, example, you can specify code like the following:

```
<action name="action name">
<dialog>
<input name="input variable name" label="label for the input dialog"
tooltip="tool tip" type="dir"/>
</dialog>
</action>
```

Using CFM pages

• In the IDE_config.xml file, specify the showResponse attribute of the Action tag as yes, as follows:

```
<action name="generate CFC" handlerid="cfcgenerator" showResponse="yes" />
```

- In the CFM handler, do the following:
 - 1 Specify the content-type value of the cfheader tag as text/xml, as follows:

```
<cfheader name="Content-Type" value="text/xml">
```

2 Create the input dialog by constructing the XML as follows:

```
<cfoutput>
<response>
<ide>
<dialog >
<input name="location" Label="Enter Location" type="dir" />
</dialog>
</ide>
</response>
</cfoutput>
```

Create HTML user interfaces

You can create an HTML user interface either by using HTML response or XML response.

Using HTML response

In the IDE_config.xml file, specify the showResponse attribute of the Action tag as yes, as follows:

```
<action name="generate CFC" handlerid="cfcgenerator" showResponse="yes" />
```

The HTML content of the CFM page appears in a dialog box. Ajax and Javascript are not supported in the HTML content. If you use links in the HTML content, the URL for the link must be an absolute URL and not a relative URL.

Using XML response

In the CFM handler, do the following:

1 Specify the content-type value of the cfheader tag as text/xml, as follows:

```
<cfheader name="Content-Type" value="text/xml">
```

2 Create the HTML user interface by constructing the XML as follows:

```
<cfoutput>
<response showresponse="true">
<ide url="http://localhost:8500/local/Dynamic%20UI%20Test/handlers/main.swf" >
<dialog width="455" height="470" />
</ide>
</response>
</cfoutput>
```

The HTML content of the specified URL appears in a dialog box.

You can also display HTML user interface through an XML response as follows:

Note: Extensions do not support relative paths for CSS and JavaScript. Ajax and JavaScript code that is specified in the CDATA section does not work. Any URL that you specify in the CDATA section must be an absolute URL.

Understanding the structure of XML response

Response

The XML response is defined within the ${\tt response}$ tag that has the following attributes:

Attribute	Description
showresponse	A Boolean value that specifies if the response must be shown to the user:
	• true
	• false
status	Displays a success or error dialog box.
	Depending on the status - success or error, the dialog appears with a relevant icon. Applicable only when message attribute is specified in IDE tag.
	This attribute is applicable only when you specify the message attribute within the IDE tag.

IDE

The IDE tag has the following attributes:

Attribute	Description
message	Displays the message that you specify in a success or error dialog box. Use status="success/error" attribute of the response tag to specify if the message must appear as an error message.
url	The URL of a page that you want to display to the user.
handlerfile	Path to the handler file that must be called when a user clicks OK in the message dialog box.
	This attribute is applicable only when input dialogs are created from an XML response.

Body

Use the body tag to specify any HTML content. The HTML content within the body tag must be specified in the CDATA section.

Dialog

The dialog tag is used to create input dialogs and has the following attributes:

Attribute	Description
height	Specifies the height of the dialog.
width	Specifies the width of the dialog.
title	Specifies the title for the dialog.
image	Specifies the path to the image that appears in the title bar.
dialogclosehandler	Path to the handler file that must be called when a user clicks Close or Cancel in the message dialog box.
	This attribute is applicable only when input dialogs are created from an XML response.

To control the height and width of the input dialogs, you use the input tag within the dialog tag.

Attribute	Description
height	Specifies the height of the dialog.
width	Specifies the width of the dialog.
title	Specifies the title for the dialog.
image	Specifies the path to the image that appears in the title bar. The path that you specify must be relative to the Extension folder.

Specifying callback commands from handlers

Handlers can request ColdFusion Builder to run the following commands:

refreshproject

- refreshfolder
- · refreshfile
- inserttext
- openfile

Note: filename and foldername values are case sensitive.

refreshproject

The refreshprojectcommand refreshes the specified project in ColdFusion Builder.

Example

refreshfolder

The refreshfolder command refreshes the specified folder in ColdFusion Builder.

refreshfile

The refreshfile command refreshes the specified file in ColdFusion Builder by sending the absolute or relative path. If you specify the relative path, specify the project name.

Example:

inserttext

The inserttext command inserts the specified text in the active editor. Selected text in the editor is replaced after this command runs.

Example:

You can also use the inserttext command to wrap text and replace text.

For example, to wrap the selected text between starttext and endtext, you can use code like the following:

```
<response>
    <ide>
        <commands>
           <command type="inserttext">
            <params>
            <param key="insertmode" value="wrap" />
            <param key="starttext" >
            <![CDATA[ Any text to be inserted in editor ]]>
            </param>
            <param key="endtext" >
            <![CDATA[ Any text to be inserted in editor ]]>
            </params>
            </command>
        </commands>
    </ide>
</response>
```

openfile

Example:

The openfile command opens the specified file for editing in ColdFusion Builder by sending the absolute or relative path. If you specify the relative path, specify the project name.

For a given response, the handler can ask ColdFusion Builder to run more than one command. For multiple commands, ColdFusion Builder runs the commands in the order in which they are received.

The XML format in which the Handler sends the response to ColdFusion Builder to run the command is as follows:

Using the Extensions view

Use the Extensions view to install, uninstall, import, and reload extensions.

If the Extensions view is not already displayed in the workbench, add the Extensions view by selecting Window > Show View > Other. Then, in the Show View dialog box, select ColdFusion > Extensions view.

Install and uninstall extensions

- 1 In the Extensions view, click and select the Archive file to install.
 - **Note:** If the extension that you are installing is shipped with ColdFusion Builder, the Archive file is available in the Extensions directory within the ColdFusion Builder installation.
- 2 The Extension Install wizard guides you through the installation.
- **3** Select the Server. If no server is configured, click Add Server to add a new server. For information about adding a server, see "Adding ColdFusion servers" on page 47.
 - You can install the same extension on different servers. For example, CF9 local server and CF8 local server. However, at any given point, only the server that the extension uses is active.
- **4** Enter the path to the ColdFusion web root (if the path is not automatically populated when selecting the server). For example, *C*:*ColdFusion9*\wwwroot\
- 5 Select a folder within the web root to install the extension. The archive file is extracted to the install location.
- 6 Click Install.

To view a brief description about the installed extension, click the extension name. If you have installed the same extension on more than one server, you can make one of the servers active. To do so, select the server that you want to make active from the Active Server drop-down list.

To uninstall an extension, select the extension in the Extensions view and click . You can uninstall an extension from the IDE only, or remove the extension from your IDE and computer's file system at the same time. When an extension is permanently removed from the file system, you cannot undo the command.

Note: If you are uninstalling an extension that is installed on multiple servers, repeat the uninstall process for every server.

Import and reload extensions

Use the Extensions view to import and reload extensions.

• You can import extensions from an existing directory into ColdFusion Builder. Click 🔁 in the Extensions view, and select the directory that contains the extension files.

Note: It is useful to import extensions when you use existing extensions to develop new extensions.

You reload an extension if you change the configuration file of an installed extension. Configuration file changes
are reflected only after you reload the extension. Click in the Extensions view to reload all the installed
extensions.

Debug and package extensions

While loading extensions from the configuration file, any errors are logged to the Eclipse log. To debug the errors, you can view the ColdFusion Builder error log by selecting Window > Show View > Other > General > Error Log. The ColdFusion Builder error log appears in the Error Log view.

To package an extension, add the following contents to a ZIP file:

- Configuration file (IDE_config.xml)
- · Handler directory that contains all the Handler CFM files

Note: Ensure that you add the configuration file and handler directory directly under the root of the ZIP file.

Use ColdFusion Builder Extension Creator to create and package extensions

The ColdFusion Builder Extension Creator wizard guides you through the process of creating and packaging extensions. The wizard guides you through creating the Configuration file (IDE_Config.xml) and Handler files (CFM), specifying metadata elements, adding context menus, and creating user interfaces.

Note: The ColdFusion Builder Extension Creator wizard is installed only if you selected Install Extensions while configuring a ColdFusion server. See the Extensions view for the list of installed extensions.

- 1 In the Navigator view, right-click the project in which you want to create the extension, and select Adobe Extension Builder > New.
- 2 Enter or browse to a location to store the extension. Select Create Folder With Extension Name to store the extension files in a folder with the same name as the extension.
- 3 Select the Extension Details tab to enter the extension name and details. You can also specify any license agreement text that must appear on installing the extension.

Specify menu contributions

Select the Menu contributions tab and click Add Menu to specify a context-menu. A context-menu is a pop-up menu that appears on a right-click action.

• Enter the name of the menu and the target view from where the menu must appear. You can specify the target view as the Navigator or Project view, RDS view, Outline view, or the CFML editor. Then, click Save Menu.

- · To specify menu items, click Add Action.
 - 1 You can associate handlers with an action. Handlers display the code generation operations that are fetched from the server. Specify the Handler ID and Handler name, and select Show Response to display the server response. Then, click Save.
 - 2 Before a handler is called, you can get user inputs. To do so, click Add Input.
 - 3 Specify the input variable name, label for the input dialog box, tooltip, and the input variable type.
 - **4** You can also specify the pattern against which the user input is validated, and the error message that appears when the validation fails.
 - **5** Select Required to specify the input field as required, and select Checked to have the check box selected, by default. Then, click Save.
- To specify filters that control the display of the menu, click Add Filter. You can specify filters at the project, folder, and file levels.

Specify handlers

Select the Handlers tab to view details about the installed handlers.

- 1 To specify a new handler, click Add Handler, and enter the necessary details.
- 2 Select Generates Response to get user inputs before calling the handler.
- 3 Specify the title of the input dialog box, and the height and width in pixels. Then, click Save Handler.

Create an extension installation wizard

Select the Install Wizards tab to create an installation wizard that guides you through the extension installation.

- 1 Specify the height and width of the wizard in pixels. You can also associate a handler with the wizard. Then, click Save.
- 2 Specify a title for the wizard, and click Save.
- 3 Specify the input variable name, label for the input dialog box, tooltip, and the input variable type. You can also specify the pattern against which the user input is validated, and the error message that appears when the validation fails.

Package the extension

- 1 In the Navigator view, right-click the ide_config.xml file and the Handler folder that contains all the Handler CFM files, and select Adobe Extension Builder > Package. The files are added to a ZIP file.
- **2** Browse to a location to store the ZIP file.

Chapter 9: Using Extensions

The following extensions are automatically installed with ColdFusion Builder if you selected the Install Extensions option when creating a server. For more information, see "Adding ColdFusion servers" on page 47.

- · Adobe CFC Generator
- ActionScript Class Generator
- · Model-Glue Assistant

The information covered here discusses how to use these extensions. It does not cover information about developing the extensions.

Note: The extension user interface is rendered in the default browser of your computer. If you want to specify the browser as Mozilla, go to the Preferences dialog box and select ColdFusion > Extensions. Then, select Use Mozilla Browser For Extensions.

Adobe CFC Generator

The Adobe CFC Generator generator generates ORM CFCs (ColdFusion Components) from database tables. The Adobe CFC Generator extension lets you create a traditional CFC or an ORM CFC from a set of tables.

Object Relational Mapping (ORM) is a programming technique that lets you define a mapping strategy to store and retrieve data from a relational database using object models. The Adobe CFC Generator lets you define the mapping for relations, specify join conditions, and generate services for the CFCs. For more information about ORM, see ColdFusion ORM in the *ColdFusion Developer Guide*.

Install Adobe CFC Generator

The Adobe CFC Generator extension is installed with ColdFusion Builder, if you selected the Install Extension option when creating a server.

If you did not install the extension when creating a server and want to install it now, see "Install and uninstall extensions" on page 87. The Adobe CFC Generator extension archive file (AdobeCfcGenerator.zip) comes packaged with ColdFusion Builder. The archive file is in the Extensions directory within the ColdFusion Builder installation.

Use Adobe CFC Generator

- 1 In the ColdFusion Builder perspective, select RDS Dataview.
- 2 If you have configured an RDS user name and password, specify the RDS user name and password.

 Note: You set the RDS password in the ColdFusion Administrator. Do not confuse the RDS password with the ColdFusion Administrator password, which is also managed through the ColdFusion Administrator.
- 3 The list of data sources available in the configured server are listed.
- 4 Select a data source and the table for which you want to generate CFCs. You can select multiple tables at once by pressing Shift and selecting the table names.
- 5 Right-click the selected tables, select Adobe CFC Generator, and select one of the following options:

Note: The Adobe CFC Generator option appears only if you right-click a table name. Clicking the data source or records within the data source does not show these options.

Create CFC Generates a ColdFusion component.

Create ORM CFC Generates an ORM CFC and maps it to the database.

Create CFC

- 1 Right-click a table in the selected data source, for example, APP.EMPLOYEES table, and select Adobe CFC Generator > Create CFC.
- 2 In the Adobe CFC Generator dialog box, do the following:
 - Specify the location to store the generated CFC.
 - Select Generate Service to automatically generate methods.

You can modify the CFC source code to provide additional functionality.

Create ORM CFC

- 1 Right-click a table in the selected data source, for example, APP.EMPLOYEES table, and select Adobe CFC Generator > Create ORM CFC.
- **2** Specify the location to store the generated CFCs.
- **3** The Adobe CFC Generator dialog box displays the selected database tables and fields in a dynamic, editable, sortable, data grid.

Note: Because the data grid is an Ajax-rich user interface, it can sometimes take a few moments to load.

You can customize the ORM CFC as follows:

- Change the CFC Name: You can edit the auto-generated CFC name in the CFC Name field.
- Change the property name: You can edit the property name in the Property Name field.
- Change the property type: To edit a property type, click the property type that appears in the Property Type column and select a property type from the drop-down list.
- Specify the primary key: You can edit the primary key settings by selecting "True" or "False" for the required column.
- You can include or exclude columns that you want to generate in the CFC by selecting or deselecting the check box next to each column name.
- Sorting data: You can sort tables and columns that appear in the data grid. The direction of the sort can be either ascending or descending. To sort table names, click the Tables column and select the sort order. To sort column data, click the column heading and select the sort order.
- 4 To generate a basic ORM CFC, click the Generate Code link.

To define relations and join conditions for the ORM CFC, do the following:

- **a** In the Relationships data grid, click Insert. A new row is inserted.
- **b** Click the Relation Name field and enter a name for the relationship. For example, you can define a relationship between the Art table and Artists table.
- **c** Select the target table from the Target Table drop-down list.
- **d** Specify the relationship type by selecting the Multiplicity drop-down list.
- e Specify a Link table, if necessary.

- f Click Save.
- **g** When you define a relationship, define a join condition. To define a join condition for the specified relationship, click the target table that you selected in step 3.
- h Click Insert in the Join Conditions data grid.
- i Select the source field from the Source drop-down list.
- j Select the target field from the Target drop-down list.
- k Click Save.
- I Click the Generate Code link.
- 5 In the Navigator view, right-click the folder that contains the CFC and select Refresh. You can modify the CFC source code to provide additional functionality.

AS Class Generator

The AS Class Generator generates ActionScript classes with or without offline metadata. Offline metadata is a part of the ColdFusion-AIR offline integration feature of ColdFusion 9. You can generate ActionScript classes either from a CFC or directly from a database table.

Install AS Class Generator

The AS Class Generator extension is installed with ColdFusion Builder, if you selected the Install Extension option when creating a server.

If you did not install the AS Class Generator extension when creating a server and want to install it now, use the AS Class Generator extension archive file (ASClassGenerator.zip). The AS Class Generator extension archive file comes packaged with ColdFusion Builder and is in the Extensions directory within the ColdFusion Builder installation. For more information on installing an extension, see "Install and uninstall extensions" on page 87.

Use AS Class Generator

The AS Class Generator application is available at the following levels:

- · RDS Dataview view
- · Project Navigator view

AS class generation is supported in the following scenarios:

- · From a database table
- From a CFC

You can generate the AS class from either an ORM CFC or a traditional CFC.

AS Class Generation from a database table

- 1 In the ColdFusion Builder perspective, select RDS Dataview.
- 2 If you have configured an RDS user name and password, specify the RDS user name and password.

Note: You set the RDS password in the ColdFusion Administrator. Do not confuse the RDS password with the ColdFusion Administrator password, which is also managed through the ColdFusion Administrator.

- 3 The list of data sources available in the configured server are listed.
- 4 Select a data source.
- 5 Right-click a table in the data source and select Generate AS Class from DB Table > Generate AS Class.

Note: The Generate AS Class from DB Table option appears only if you right-click the table name. Clicking the data source or records within the data source does not show these options.

- **6** Enter the following details in the Generate AS Class dialog box.
 - Specify or select a location to store the ActionScript class files.
 - Select the Include AS Metadata Tags check box to include the following metadata tags:

[RemoteClass] Maps the ColdFusion CFC or Java objects on the ColdFusion server with the generated ActionScript class

[Entity] Indicates that the generated ActionScript class has to be persisted to the AIR SQLite database as a table. This tag is a ColdFusion-AIR offline integration tag.

[Id] Specifies the AS Class property as a primary key after the ActionScript class is persisted to the AIR SQLite database table.

• Enter the path to the remote CFC class using dot notation relative to the web root. For example, if the path to the CFC is C:\ColdFusion9\wwwroot\CFProj\xyz.cfc, the dot notation path is CFProj.xyz

Note: This entry is ignored if you have not selected the AS Metadata Tags check box.

- Enter the name of the package. The naming convention is the same as the ActionScript naming convention.
- 7 The ActionScript Class file is created with the naming convention databasetablename.as

Reviewing the generated ActionScript Class file

The following code is an example of an ActionScript class file - Employees. as that is generated from the Employees table in the cfdocexamples data source.

Code	Description
package package1	The package is created with the name "package1"
[RemoteClass(alias="cfproj.xyz")]	The ActionScript Class maps with cfproj/xyz.cfc on the server.
[Entity] public class EMPLOYEES { [Id] public var EMP_ID:int; public var FIRSTNAME:String; public var LASTNAME:String; public var EMAIL:String; public var PHONE:String; public var DEPARTMENT:String; public var LOCATION:String; public var IM_ID:String; public var IM_ID:String; public function EMPLOYEES() { } }	The class name is the same as the database table name. Each property in this class corresponds to a column in the Employees database table. The data type of each property is mapped automatically after introspecting the column data type.

AS Class Generation from CFC

From an ORM CFC

1 Create an ORM CFC.

Note: CFCs for which ActionScript classes are generated must be within the ColdFusion web root.

- 2 In the Project Navigator, right-click the ORM CFC and select Generate AS Class from CFC > Generate AS Class.
- 3 Enter the following details in the Generate AS Class dialog box.
 - Specify or select a location to store the ActionScript class files.
 - Enter the name of the package. The naming convention is the same as the ActionScript naming convention.
 - Select the Include AS Metadata tags check box to include the [RemoteClass] tag.
 - Select the Include CF-AIR Offline Metadata check box to include the following tags:
 - [Entity]
 - [Id]
 - If the ORM CFC already has the necessary information like, primary key and data type for each property, you need not enter the ColdFusion data source.

From a traditional CFC

- 1 In the Navigator view, right-click the CFC and select Generate AS Class from CFC > Generate AS Class.
 Note: CFCs for which ActionScript classes are generated must be within the ColdFusion web root.
- 2 Enter the following details in the Generate AS Class dialog box.
 - Specify or select a location to store the ActionScript class files.
 - Enter the name of the package. The naming convention is the same as the ActionScript naming convention.
 - Select the Include AS Metadata tags check box to include the [RemoteClass] tag.
 - Select the Include CF-AIR Offline Metadata check box to include the following tags:
 - [Entity]
 - [Id]
 - If the primary key and data type for each property is not specified in the CFC, enter the ColdFusion data source name.

Points to remember

- For CF-AIR offline integration, column-specific metadata tag [Column] additions are not currently supported. However, you can manually add the column-specific metadata tags after the ActionScript class file is generated.
- RDS does not provide information about the primary key of a table in the data source. Use the cfdbinfo tag to identify the primary key. The cfdbinfo tag does not support ODBC drivers including Microsoft Access. Hence, for unsupported data sources, you manually define the Id column in the generated ActionScript Class file.
- CFCs for which ActionScript class files are generated must be within the ColdFusion web root.
- In an ORM CFC, datatype/type is an optional attribute of the cfproperty tag. If this attribute is not present in the CFC, ActionScript class files are not generated. To ensure that the ActionScript class files are generated, specify the ColdFusion data source. Data type information is retrieved from the database table and the ActionScript class file is created.

Model-Glue Assistant

Model-Glue Assistant is a ColdFusion Builder application that is designed to help you get started with Model-Glue.

Model-Glue is a web application framework to develop ColdFusion web applications (For more information on Model-Glue, see http://docs.model-glue.com).

Prerequisites to use Model-glue Assistant extension

Before you use the Model-Glue Assistant extension, install the following supporting frameworks:

- Model-Glue Framework (You can download from www.model-glue.com)
- ColdSpring Framework (You can download from www.coldspringframework.org)
- Reactor Framework (You can download from www.reactorframework.org)

If you already have the supporting frameworks installed on your computer, you do not have to reinstall the frameworks again.

The Model-Glue Assistant is designed to work with Model-Glue version v2.0.304. If the version of Model-Glue on your computer is other than the specified version, update Model-Glue Assistant.

Install Model-Glue Assistant extension

The Model-Glue Assistant extension is installed with ColdFusion Builder, if you selected the Install Extension option when creating a server.

If you did not install the Model-Glue Assistant extension when creating a server and want to install it now, see "Install and uninstall extensions" on page 87. The Model-Glue Assistant extension archive file (ModelGlue Assistant.zip) comes packaged with ColdFusion Builder. The archive file is in the Extensions directory within the ColdFusion Builder installation.

Create a ColdFusion project

- 1 Create a ColdFusion project under the web root. See "Creating a ColdFusion project" on page 55 for details.
- **2** In the Add Existing Sources and Referenced Project dialog box, ensure that you select the ModelGlue Assistant Application check box in the list of Applications.
- 3 Once you create the ColdFusion project, right-click the project in the Project Navigator and select Refresh to see the files and folders that are created. The ModelGlue.xml and ColdSpring.xml files in the Config folder are automatically configured for your project.
- **4** To check if the Model-Glue Assistant is configured correctly, enter the following URL in your web browser: http://localhost/project name/index.cfm
 - The ModelGlue 2.0 web page appears with the message that it is up and running. You see many debug messages that you can comment out; see "Debug Trace Toggle" on page 96 for details.

Use Model-Glue Assistant

In the Project Navigator, right-click the configured project and select ModelGlue Assistant. You see the following options. Relevant code is generated for each of following actions.

Add Event

In Model-Glue, when you add an event, you associate a CFM page with the event. When you add an event, the code that is added to the CFM file is typically as follows:

The code includes a handler name, a message to broadcast when the event runs, and a view that is associated with a CFM file. For more information, see http://docs.model-glue.com/.

The Model-Glue Assistant lets you add this code easily as follows:

- 1 Right-click the project in the Navigator and select ModelGlue Assistant > Add Event. Enter the following details in the Add Event dialog box.
- **2** Enter a name for the event.
- 3 Enter a broadcast message, if necessary. The message that you enter is broadcast when the event runs.
- 4 Enter a view name.
- **5** Enter the location to store the CFM file associated with the view. The location must be a folder or subfolder within the Views folder of the project.
- 6 Enter a value name and value, if necessary.
- 7 To check if the event is added, enter the following URL in your web browser:

http://localhost/project name/index.cfm?event=event name

Model-Glue Assistant displays a default message in the web page. To change this message, edit the CFM file that you associated with the view.

Generated code

Model-Glue Assistant adds an event handler entry to the ModelGlue.xml file.

Debug Trace Toggle

The Debug Trace Toggle functionality lets you toggle the display of the Model-Glue web page between showing the debugging messages and clearing them.

- 1 Right-click the project in the Navigator and select ModelGlue Assistant > Debug Trace Toggle.
- **2** Enter the following URL in your web browser: http://localhost/project name/index.cfm The debugging messages are removed.
- **3** To display the debugging messages, right-click the project in the Navigator and again select ModelGlue Assistant > Debug Trace Toggle.

Generated code

Model-Glue Assistant toggles the value of the debug node in the ColdSpring.xml file.

Enable Reactor

For database-related events, Model-Glue works with the Reactor framework. To get Model-Glue working with Reactor, enable Reactor. To enable Reactor, clear comments on the Reactor entries in the ColdSpring.xml file (located in the Config folder of your project).

• Right-click the project in the Navigator and select ModelGlue Assistant > Enable Reactor.

Generated code

Model-Glue Assistant clears the comments on the Reactor entries in the ColdSpring.xml file.

Creating Scaffolds

Using the Model-Glue Assistant you can create Scaffolds that let you quickly create basic user interfaces to the database table. For more information on Scaffolds, see http://docs.model-glue.com and http://livedocs.reactorframework.com

- 1 In the ColdFusion Builder perspective, select RDS Dataview.
- 2 If you have configured an RDS user name and password, specify the RDS user name and password.

Note: You set the RDS password in the ColdFusion Administrator. Do not confuse the RDS password with the ColdFusion Administrator password, which is also managed through the ColdFusion Administrator.

- 3 The list of data sources available in the configured server are listed.
- 4 Select a data source.

Note: Scaffolds do not support all type of data sources. For information about the supported data sources, see http://livedocs.reactorframework.com/

5 Right-click a table in the data source, and select ModelGlue Assistant > Create Scaffold Entry.

Note: The ModelGlue Assistant option appears only if you right-click the table name. Clicking the data source or records within the data source does not show the Create Scaffold Entry option.

Enter the following details in the Create Scaffold Entry dialog box.

- **6** Select the project configured for Model-Glue Assistant.
- 7 Enter the data source user name and password.

Note: You set the data source user name and password in the ColdFusion Administrator. The data source password is different from the RDS password and the ColdFusion Administrator password.

- **8** Select the data source type from the DB Type drop-down list.
- **9** To check if the Scaffold entry is added, enter the following URL in your web browser:

http://localhost/project name/index.cfm?event=table name.list

- **10** After verifying that the Scaffold entry is created, you see that the following files are created under the Scaffolds folder in the project:
 - · dsptablename.cfm
 - dsptablenameList.cfm
 - frmtablename.cfm

Generated code

- A Scaffold entry is added to Reactor.xml for the selected table. Table relationships are not added.
- The Reactor configuration in ColdSpring.xml is updated to point to the correct data source.

· A Scaffold object entry is added to ModelGlue.xml

Update Model-Glue Assistant

You can update the Model-Glue Assistant extension to the version of Model-Glue and supporting frameworks on your computer.

- 1 Go to the location in the web root where you have installed Model-Glue Assistant.
- 2 In the Model-Glue Assistant folder, you see a Handlers folder and the ide_config.xml file.
- **3** To update the Model Glue Application template files to point to the version of Model-Glue on your computer, edit the modelapp.ini file in the Handlers folder. The code in the modelapp.ini file is as follows:

Specify the absolute path to Model-Glue Application Template folder in the location attribute.

For example, location="C:\ColdFusion9\wwwroot\ModelGlueApplicationTemplate"

Model-Glue Assistant performs string-handling operations for code generation. To customize the code generated, you can update the CFM files in the Handler folder, as required.